CONFORMANCE TEST SUITE USER MANUAL

for Testing Interface and Application Code against the $FACE^{TM}$ Technical Standard 3.0

CTS Version 3.0.7



NAVAIR Public Release 2024-0004 Distribution Statement A -"Approved for public release; distribution is unlimited"

Copyright (c) Vanderbilt University, 2024

(adapted from "original work"; Copyright (c) 2018-2019 Georgia Tech Applied Research Corporation; Copyright (c) 2018 Vanderbilt University)

ALL RIGHTS RESERVED, UNLESS OTHERWISE STATED

This software, authored by Vanderbilt University under a contract awarded to and managed by Precise Systems, was funded by the U.S. Government under Contract No. N00178-14-D-7875 and the U.S. Government has unlimited rights in this software. An "unlimited rights" license means that the U.S. Government can use, modify, reproduce, release or disclose computer software in whole or in part, in any manner, and for any purpose whatsoever, and to have or authorize others to do so.

This work was originally developed under Contract No. FA8075-14-D-0018 awarded to the Georgia Tech Applied Research Corporation (GTARC) by the U.S. Government for the Georgia Tech Research Institute (GTRI) and Institute for Software Integrated Systems (ISIS), Vanderbilt University.

GTARC and Vanderbilt University disclaim all warranties with regard to this software, including all implied warranties of merchantability and fitness for a particular use or purpose, validity of any intellectual property rights or claims, or noninfringement of any third party intellectual property rights. In no event shall GTARC or Vanderbilt University be liable for any special, indirect or consequential damages or any damages whatsoever resulting from loss of use, data or profits, whether in an action of contract, negligence or other tortious action, arising out of or in connection with the use or performance of this software.

Vanderbilt University acknowledges The Open Group for permission to include text/figures derived from its copyrighted Future Airborne Capability Environment[®] Reference Architecture. FACE is a trademark of The Open Group in the United States and other countries.

NAVAIR Public Release 2024-0004

Distribution Statement A -"Approved for public release; distribution is unlimited"

HANDLING AND DESTRUCTION NOTICE: Comply with distribution statement and destroy by any method that will prevent disclosure of the contents or reconstruction of the document.

Future Airborne Capability Environment[®] Reference Architecture, 2012 The Open Group. FACE is a trademark of The Open Group in the United States and other countries.

Table of Contents

1. Introduction.	6
1.1. Context	6
1.2. Tools Contained in the Test Suite	6
1.2.1. Conformance Testing Workflow	7
2. Installation	10
2.1. Installation on Linux (CentOS 7/RHEL 7)	10
2.1.1. User Prerequisites.	10
2.1.2. System Requirements	10
2.1.3. Language-Specific Prerequisites	10
GCC/G++ 4.8.5	11
Python 2.7	11
Java 8 JDK	11
Ant 1.9.x.	13
2.1.4. Installation of CTS	13
Environment Variables	13
2.1.5. Running CTS	14
Launching CTS	14
2.2. Installation Variance for CentOS 8/RHEL 8	15
2.3. Installation on Windows (Windows 10)	16
2.3.1. User Prerequisites.	16
2.3.2. System Requirements	16
2.3.3. Language-specific Prerequisites	16
2.3.4. Detailed Instructions for Installing Prerequisites	17
Python 2.7	17
Java JDK 8	
MSYS2 (for C/C++/Ada samples only)	22
Ant 1.9.x.	25
Enable Long Paths in Windows 10	26
2.3.5. Installation of CTS	27
Installation Variance for Windows Cygwin/GCC Toolchains	27
2.3.6. Running CTS	27
3. Theory of Operation	29
3.1. Introduction to Methodology	29
3.2. Target Linker Method	30
3.3. Host Linker Method	31
3.4. Additional Methodology Information	31
3.4.1. OSS Testing Methodology	31
3.4.2. Java Testing Methodology	31

4. Toolchain Configuration File	32
4.1. Introduction	32
4.2. Toolchain Files List	32
4.3. Building a Toolchain Configuration File	33
4.3.1. General Tab	33
4.3.2. File Extensions Tab	34
4.3.3. Tools Tab	35
4.3.4. Compiler Specific Tab	38
Compiler Specific Functionality	38
Configuration	39
4.3.5. Notes Tab.	41
5. Project Configuration File	43
5.1. Introduction	43
5.2. Project Files List	43
5.3. Building a Project Configuration File	44
5.3.1. General Tab	44
5.3.2. Data Model Tab	45
5.3.3. Gold Standard Libraries Tab	46
5.3.4. Objects/Libraries Tab	47
5.3.5. Notes Tab.	53
5.3.6. Project Info Tab	53
6. Sample Project and Toolchain Configuration Files	55
6.1. Build Flags	55
6.2. Linux Generation	56
6.3. Windows Generation	56
6.3.1. Regarding Failing Test Results and Shared Data Model	58
7. Testing a UoC	59
7.1. Overview	59
7.2. Testing a Portable Components Segment (PCS) UoC	59
7.2.1. What the User Must Provide	59
7.2.2. Test Procedures	60
Providing Project Context	60
Generating the Gold Standard Libraries	66
Factory Functions	67
Validating and Testing a Project	68
7.3. Testing a Platform Specific Services Segment (PSSS) UoC	69
7.3.1. What the User Must Provide	69
7.3.2. Test Procedures	69
Providing Project Context	69
Generating the Gold Standard Libraries	75
Factory Functions	76

Validating and Testing a Project	77
7.4. Testing a Transport Services Segment (TSS) UoC	
7.4.1. What the User Must Provide	
7.4.2. Test Procedures	
Providing Project Context	
Generating the Gold Standard Libraries	
Factory Functions	85
Validating and Testing a Project	86
Special Verification Cases	87
7.5. Testing an I/O Services Segment (IOS) UoC	87
7.5.1. What the User Must Provide	87
7.5.2. Test Procedures	87
Providing Project Context	87
Generating the Gold Standard Libraries	
Factory Functions	
Validating and Testing a Project	
7.6. Testing an Operating System Segment (OSS) UoC	
7.6.1. What the User Must Provide	
7.6.2. Test Procedures	
Providing Project Context	
Generating Gold Standard Libraries	
Factory Functions	
Validating and Testing a Project	
7.7. Testing a Data Model	
7.7.1. What the User Must Provide	
7.7.2. Test Procedures	
7.8. Considerations for Testing an Ada Segment	106
7.9. Considerations for Testing a Java Segment	106
7.10. Viewing Test Suite Results	
Appendix A: References	
Appendix B: Using the CTS Via Command Line Interface (CLI):	
Appendix C: Glossary	
Appendix D: Constraints	
Appendix E: Known Issues	
Appendix F: Acknowledgments	
Appendix G: Approved Corrections to Technical Standard by CTS Version.	
Appendix H: CTS Treatment of Default Values for Element/Composition Attributes	

1. Introduction

This Guide is intended to show the user how to install and effectively use the Conformance Test Suite (CTS). The CTS tests Units of Conformance (UoCs) and data models that meet a subset of the requirements in the FACE[®] Technical Standard, Edition 3.0. All requirements the CTS is required to test are defined in the Conformance Verification Matrix (CVM), provided by the FACE Consortium. All types of UoCs may be tested with the CTS, including:

- 1. Portable Components Segment (PCS) UoCs
- 2. Platform Specific Services Segment (PSSS) UoCs
- 3. Transport Services Segment (TSS) UoCs
- 4. I/O Services Segment (IOSS) UoCs
- 5. Operating System Segment (OSS) UoCs

Testing procedures for each segment are listed in the sections contained in this user manual.

1.1. Context

Each of edition of the FACE Technical Standard has a corresponding line of CTS applications. The CTS version identifier follows the pattern 3.X.Y, where X is a number that defines the minor edition of the Technical Standard, and Y to version of the CTS released to support the given Technical Standard. For example, CTS 3.1.0 represents supporting the 3.1 edition of the Technical Standard and is the initial release of the CTS. This document refers to CTS versions in support of FACE Technical Standard, Editions 3.X and will henceforth be referred to as "the CTS" unless otherwise delineated.

1.2. Tools Contained in the Test Suite

The CTS's graphical user interface (GUI) allows for a user-friendly approach for FACE conformance testing and it is the method in which users of the CTS are expected to use the tool. Additionally, the CTS is comprised of multiple, separate tools that work together to test software components against the FACE Technical Standard and produce a conformance test result.

Although the user is expected to interact with CTS through the GUI, it is beneficial to understand from a high-level the specialized tools the CTS uses and how they work together to test for conformance. There are four tools contained in the CTS:

- 1. UsmIDLGenerator/DIG (Data Model to IDL Generator)
 - The UsmIDLGenerator/DIG generates the IDL (Interface Definition Language) for the platform data types and views specified by a Unit of Portability (UoP) in a USM (UoP Supplied Model). Used at CTS runtime, the generated IDL is compiled into source code for the programming language that the candidate UoC is written.

NOTE

The term "Unit of Portability" (or UoP) is a general term referring to either a PCS or PSSS UoC. This document attempts to limit uses of the term "UoP" to references to a USM and its contents. Any occurrence of the term not meeting this intent can be assumed to be a synonym for "UoC".

- 1. Ideal
 - Ideal is a translator that converts FACE interfaces, defined in IDL, using the programming language mappings described in the FACE Technical Standard for Ada, Java, C99, and C++03.
 Ideal is used by the CTS to generate language specific code from the output of the USmIDLGenerator/DIG.
- 2. DMVT (Data Model Validation Tool)
 - The DMVT takes the Shared Data Model (SDM) and a UoC's USM as inputs to test the USM for adherence to the data architecture specification in the FACE Technical Standard. For UoC's that require a USM for testing, the CTS invokes the DMVT first to ensure the USM is meets the Standard before proceeding with testing. The SDM is available for download on The Open Group's website at https://www.opengroup.org/face/docsandtools.
- 3. FACE Conformance Application
 - The FACE Conformance Application refers to the software pieces of the CTS for the front-end GUI, backend processes to test for FACE conformance and the generation of the FACE conformance report after a UoC is tested.

The overall testing workflow and how the tools are used is summarized in the following section.

1.2.1. Conformance Testing Workflow

The figure below provides details of the high-level workflow on how each of the CTS tools interact with one another. The figure also details an example for intended UoC development and UoC conformance testing process.

Specific instructions on how to test a specific UoC is contained within this user manual in the Project Configuration Files, Toolchain Configuration Files and Testing a UoC sections.



Figure 1. The workflow of FACE development and conformance testing.

By following the numerical arrows in the figure, the user can see the process of developing a UoC and passing it through the CTS:

- 1. The user must create or import a toolchain configuration file for the user's specific compiler/linker/archiver tools, either from scratch or basing it off one of the sample toolchains. The user must also create or import The Project Configuration file by specifying the profile, segment, interfaces the UoC implements and interfaces it uses, and the USM and corresponding SDM locations (if appropriate).
- 2. The user must click on the "Generate GSLs/Interface" button in the toolbar.
- 3. The USM's location is taken from the configured project configuration file. The USM is parsed for TSS Typed interfaces and/or Life Cycle Management (LCM) Stateful interfaces and be sent to the UsmIDLGen/DIG tool.
- 4. The UsmIDLGen/DIG tool translates the data structures and typed interfaces based on the USM to IDL.
- 5. Ideal generates the IDL into interface headers (C/C++/Ada spec files/Java) files based on the UoC programming language. These files will be placed into a subfolder of the project folder as the "Gold Standard" folder (the relative of the subfolder is include/FACE). This process also generates a text file in this location with all the include paths the user should use to compile their code for conformance.
- 6. The user gathers the generated text file
- 7. Based on the CTS Factory Functions header (the generated text file), the user writes their implementation code (called Factory Functions) that implements each interface being provided by the UoC from these generated interfaces created in Step 5.
 - a. Implement each UoC interface based on the language constraints:
 - i. For C++ and Java, the implementation is a derived class for each interface being provided. The base/abstract class is the interface class provided in the Gold Standard Library subfolder include/FACE as generated by the CTS.
 - ii. For C and Ada, one must create implementations of the functions/procedures.

- b. Next, for each FACE interface that the UoC is to "use" (access), the user must also implement the Injectable interface for that interface.
- 8. The user adds the Factory Functions to the .pcfg file in the Objects/Libraries tab
- 9. The user compiles their UoC code using the generated headers or spec files or Java files (depending on language) and the include paths (compiler paths or class paths) provided in the generated text file.
- 10. The user adds the object code to the CTS and runs the Conformance test by pressing the "Test UoC Conformance" button.
- 11. The FACE Conformance Application invokes the DMVT/DAVT, sending the USM and SDM location
- 12. The DMVT validates the USM based on the SDM and sends back the result.
- 13. The FACE Conformance Application:
 - a. Tests source files for injectables that are generated.
 - b. Compiles CTS Factory Functions using the user-provided Factory Functions file.
 - c. Tests files (generated and CTS-provided) are compiled and linked with the UoC object(s), CTS Factory Functions, and GSL libraries into a series of executables (that never are run, as the CTS only tests to see if a UoC correctly links with the test executables).
 - d. Link test is performed with limited GSL libraries to test for inter-UoC restricted calls.
- 14. A PDF conformance report is generated based on the results of step 13. The PDF report contains all test logs and stack traces to those logs so the user can alter the UoC if there are any failures.

2. Installation

2.1. Installation on Linux (CentOS 7/RHEL 7)

2.1.1. User Prerequisites

To successfully install the CTS, the user must have root permission to access network-based repositories (such as "yum"), package installation privileges, and privileges to change file permissions (via "chmod").

These permissions are necessary, as some dependencies are not installed by default.NOTE It is acknowledged that the CTS installation process is not optimized for installation on government machines or on machines that restrict installation.

2.1.2. System Requirements

Before installation, check the system requirements below to ensure the test suite will run on the user's designated machine. The CTS has been developed and tested on CentOS 7. It is highly recommended to use this version of Linux for the installation of this version of the CTS, as using other distributions will have varying results.

Minimum Requirements	
Operating System	CentOS 7, Red Hat Enterprise Linux (RHEL) 7
HDD/SDD	3 GB
RAM	4 GB
An Internet connection	

Table 1. The minimum requirements to run on a Linux-based system.

For setting up under virtual machine, make sure that the allocated drive has at least 15GB. Doing so will give the VM enough space to install its operating system, all of prerequisites, and the CTS itself.

Table 2. Dependencies that are required to successfully install the CTS on a Linuxbased system.

System Dependency
Python 2.7 installation, with: → zlib - a Python compression library → setuptools - a package used to help install and uninstall other Python packages
Java 1.8 JDK
Any PDF viewer

2.1.3. Language-Specific Prerequisites

The following section lists dependencies that UoCs written in a specific language require.

Table 3. UoC Testing Dependencies for Linux-based systems.

Language	Language Dependency
С	GCC/G++ version 4.8 or higher
C++	GCC/G++ version 4.8 or higher
Ada	GNAT for GCC version 4.8 or higher
Java	Java JDK 1.8
Java	Linux alternatives utility package (if more than 1 version of Java is installed)
Java	Ant 1.9.0 or higher
Java	Browser (if not installing on the command line, which is recommended)

Table 4. UoC Testing Dependencies for Linux-based systemss.

Language	Library	Language Dependency
Posix	libarchive-devel	version 3.1.2 or higher
Posix	zlib-devel	version 1.2.7 or higher

Details on how to install these dependencies are contained in the following sections. It is important that the user attempt to install the CTS on a machine with at least the minimum specifications as stated in the Table 1. The following subsections will guide the user on how to install each of these prerequisites.

GCC/G++ 4.8.5

Install gcc/g++ from yum package:

```
sudo yum install gcc gcc-c++ gcc-gnat
```

This is necessary for C/C/Ada projects. This command will also install required dependencies for the gcc, gcc-c, and gcc-gnat packages.

Python 2.7

Python 2.7.5 is installed by default on CentOS 7/RHEL 7. If it is not already installed then install python 2.7.

The following python packages are included with CTS. Do not use pip to install them as the pip installed packages can interfere with the CTS included packages and cause execution errors. Remove these packages if they were installed previously via pip.

- protobuf-2.6.1-py2.7.egg
- pyparsing-2.0.1-py2.7.egg
- stringtemplate3-3.1-py2.7.egg

Java 8 JDK

The user must install Java 8 JDK. The best way to do this is download via browser, as the user needs to accept the license agreement before they can download. The user may download from the url:

https://www.oracle.com/java/technologies/javase/javase8u211-later-archive-downloads.html. It is recommended to download the "Linux x64" .rpm file of the latest version of Java 8 for a quick install.

The user must navigate to the directory where they downloaded the rpm and execute the following commands.

```
sudo yum install jdk-8uXXX-linux-x64.rpm
```

Optional note: If the user has different major versions of Java present on their installation system, the 'alternatives' utility may be used. The utility allows the user to use and manage different versions of applications in their environment via symbolic links. By default, it is installed in most Linux distributions. If it is not installed, the user must install it via the normal means for installing packages for their Linux distribution. Then, the user must initialize both the "java" and "javac" to the alternatives package. It is important to include both, as "java" is used to execute Java bytecode, and "javac" is used to compile Java programs.

sudo /usr/sbin/alternatives --install /usr/bin/java java
/usr/java/jdk1.8.0_XXX/bin/java 2000

```
sudo /usr/sbin/alternatives --install /usr/bin/javac javac
/usr/java/jdk1.8.0_XXX/bin/javac 2000
```

If the user executes,

```
sudo alternatives --config java
```

they should see a selection display that contains the locations of all of the Java programs installed on the machine, each with a numeric id. The user can select the Java program they want to be associated with the name "java" by entering the corresponding id.

```
There are 4 programs which provide 'java'.

Selection Command

1 java-1.7.0-openjdk.x86_64 (/usr/lib/jvm/java-1.7.0-openjdk-1.7.0.261-2.6.22.2.el7_8.x86_64/jre/bin/java)

* 2 java-1.8.0-openjdk.x86_64 (/usr/lib/jvm/java-1.8.0-openjdk-1.8.0.282.b08-1.el7_9.x86_64/jre/bin/java)

3 /usr/lib/jvm/jre-1.6.0-openjdk.x86_64/bin/java

+ 4 /usr/java/jdk1.8.0_161/jre/bin/java

Enter to keep the current selection[+], or type selection number:
```

Figure 2. Configuring Default Java Using "alternatives" Utility

If the user executes,

```
sudo alternatives --config javac
```

they should see a selection display that contains the location of all of the Java compilers installed on the machine. The user can select the Java compiler program they want to be associated with the name "javac" by entering the corresponding id. The user must set 2 environment varibales for java. It is recommended to add this to the user's permanent environment or via terminal startup script at ~/.bashrc. "JDK8_HOME" variable is defined to point to the base directory of the JDK 8 installation. "JAVA_HOME" variable is set to the "JDK8_HOME" variable.

export JDK8_HOME=/usr/java/jdk1.8.0_XXX
export JAVA_HOME=\$JDK8_HOME

Ant 1.9.x

Execute the following command to install Ant:

sudo yum install ant

Note: The default installation version for Ant may be different than 1.9 for the user's system. Check the package version in yum before installing. This prerequisite is only required to build sample UoCs for Java. The user can exclude the Java UoCs when building sample UoCs, if desired.

2.1.4. Installation of CTS

To install the CTS, simply extract the archive file (zip or tar.gz) to a folder somewhere where the user has read/write/executable access.

Environment Variables

The user must have set the environment variables to correctly hook in with the proper supporting tools. It is recommended to add environment variables to the user's permanent environment or via terminal startup script at ~/.bashrc. It must be defined and exported.

Below is a summary of all the environment variables that must be set using .bashrc as the example. Please note that the user must source the .bashrc or restart the terminal after making changes.

Open ~/.bashrc using nano or another editor:

export JDK8_HOME=/usr/java/jdk1.8.0_XXX
export JAVA_HOME=\$JDK8_HOME

Please note that the JAVA_HOME variable is used to run the CTS GUI. JDK8_HOME should reflect the version of Java the user is currently using.

Save, exit the terminal, and start a different terminal to let the environment variables take effect in the new terminal. Alternatively the user can source the .bashrc file in the same terminal.

```
source .bashrc
```

The user will now have Java 8 as a dependency. To test if the environment variables were set

successfully, the user may execute:

echo \$<variable name>

This provides the user with what was set to the specified environment variable.

2.1.5. Running CTS

Ensure you are running in an environment that has all of the above environment variable settings refreshed. If in doubt, start a new terminal window. Ensure that this setup is correct by running:

```
java -version
```

Check that this is a Java 8 version, *not the OpenJDK1.8 version*. Open JDK is not supported as it does not provide JavaFX, which the CTS GUI uses. If it is the OpenJDK version (or is not Java 8 at all), execute:

sudo alternatives --config java

When prompted, enter the number corresponding to the JDK 1.8.

Next, ensure that javac is set to use the Java 8 JDK by executing the following commands:

sudo alternatives --config javac

When prompted, enter the number corresponding to the JDK 1.8.

Launching CTS

Navigate to the top-level directory of the CTS installation, and execute the below command in a terminal:

./run_CTS_GUI.py

To produce a verbose output in the execution terminal:

```
./run_CTS_GUI.py -v
```

This will launch the conformance main menu as shown in below figure.

File I	Run	Help				$\mathbf{\hat{n}}$
Future Airbor	G ne C apability	Environment*	Welcor Supporting	n FA	e to FACE Conformance Test Suite	e
Rece	ent Pr	ojects			Quick Start	
					Run Conformance Test	
					Create a Project Configuration	
					🛃 Create a Toolchain Configuration	
	No R	ecent Proje	ects		😵 Preferences	
					Cocumentation	

Figure 3. The CTS home screen.

2.2. Installation Variance for CentOS 8/RHEL 8

The system requirements and prerequisite requirements for running the CTS on CentOS 8 are the same as CentOS 7.

- GCC/G++ 4.8.5
- Python 2.7
- Java 8 JDK

The installation instructions for prerequisites on CentOS 7 applies to CentOS 8 with the exception of installating Python 2.7. By default CentOS 8 doesn't have an unversioned system-wide python command to avoid locking the users to a specific version of Python. Instead, the user has the option to install, configure, and run a specific Python version.

The steps to install Python 2.7 are as follows:

```
sudo dnf install python2
sudo alternatives --set python /usr/bin/python2
```

Please see installation instructions for all other prerequisites from section Section 2.1.3.

Please see instructions for running and launching CTS from sections Section 2.1.5 and Section 2.1.5.1.

Note that Ada cannot be tested on CentOS 8 due to the lack of GNAT support on CentOS 8.

2.3. Installation on Windows (Windows 10)

2.3.1. User Prerequisites

To successfully install the CTS, the user must have permissions to save downloaded files to the filesystem and software installation privileges as well as access to the internet for downloading prerequisite software.

NOTE

It is acknowledged that the CTS installation process is not optimized for installation on government machines or on machines that restrict installation.

2.3.2. System Requirements

Before installation, check the system requirements below to ensure the test suite will run on the user's designated machine.

•	
Minimum Requirements	
Operating System	Windows 10 64-bit
HDD/SDD	25 GB
RAM	8 GB
An Internet connection	

Table 5. The minimum requirements to run on Windows.

The processor and graphics card are not included in Table 5, as the CTS is not processor or graphically intensive.

Table 6 represents an overview of the prerequisites needed to install and execute the CTS. Please carefully follow the instructions in "Detailed Instructions for Installing Prerequisites" for installing each.

Table 6. The prerequisites needed to install CTS on a Windows system.

System Requirements
Python 2.7 with zlib and setuptools support
Java 1.8 SDK
Any PDF viewer

2.3.3. Language-specific Prerequisites

The following section lists dependencies that UoCs written in a specific language require. The installation of each dependency will be detailed in the "Detailed Instructions for Installing Prerequisites" for the user's operating system, contained in this document.

Table 7. UoC Testing Dependencies for Windows 10.

Language	Language Dependency	msys2.0 package
C/C++/Ada	msys 2.0	mingw-w64-x86_64-toolchain
C/C++/Ada	msys 2.0	base-devel
C/C++/Ada	msys 2.0	msys2-devel
C/C++/Ada	msys 2.0	make
Java	Java JDK 1.8	
Java	Ant 1.9.0 or higher	

The language dependency for C/C++/Ada requires msys2 to install some required software packages. Msys2 is a software distribution package and building platform for Windows, intended to provide a POSIX compatibility layer that Windows distributions do not provide. It provides a bash shell and the ability to build native windows applications using the MinGWw64 toolchains.

2.3.4. Detailed Instructions for Installing Prerequisites

It is recommended to install the CTS on a machine with at least the minimum specifications stated in Table 5. The user must have permission to install and run programs on the machine.

Python 2.7

The CTS backend (conformance tests, logic, etc.) runs Python 2.7, and thus must be installed by the user.

Download and install Python 2.7.x 64 bit for Windows by going to https://www.python.org/downloads/release/python-2715/. It is recommended to download the installer, rather than install manually.

Navigate to the "Environment Variables" menu, as done for the Java 8 installation. The user must add the Python installation folder to their SYSTEM environment path variable at the top of the list (ex C:\Python27).

IMPORTANTThe CTS uses Python 2.7 and will not function correctly using Python 3.IMPORTANTPython 2.7 must appear before all other directories providing Python (e.g., MSYS2).



Figure 4. They Python 2.7 environment variable near the top of the list, with the variable is outlined in red.

The following python packages are included with CTS. Do not use pip to install them as the pip installed packages can interfere with the CTS included packages and cause execution errors. Remove these packages if they were installed previously via pip.

- protobuf-2.6.1-py2.7.egg
- pyparsing-2.0.1-py2.7.egg
- stringtemplate3-3.1-py2.7.egg

Java JDK 8

The following subsections detail how to install Java 8 to the user's system.

Download or acquire JDK 8 from Oracle for Windows 64 bit and install:

http://www.oracle.com/technetwork/java/javase/downloads/jdk8-downloads-2133151.html . The best way to do this is via a browser, as you need to accept the license agreement.

Next, create a SYSTEM-level environment variable JDK8_HOME set to the folder where you installed

JDK8. To do this, the user must press the start button on their keyboard and type "environment variables." Select "Edit the system environment variables." When the GUI pops up, the user must select "Environment Variables" near the bottom of the GUI.

omputer Name Hardware	Advanced	System Protect	ion Remote
You must be logged on a	s an Adminis	trator to make m	ost of these changes.
Performance			
Visual effects, processo	r scheduling	, memory usage,	and virtual memory
			Settings
User Profiles			
Desktop settings related	d to your sigr	i-in	
			Settings
Startup and Recovery			Settings
Startup and Recovery System startup, system	failure, and d	lebugging inform	Settings
Startup and Recovery System startup, system	failure, and d	lebugging inform	Settings
Startup and Recovery System startup, system	failure, and d	lebugging inform	Settings ation Settings
Startup and Recovery System startup, system	failure, and d	lebugging inform	Settings Settings

Figure 5. The system properties interface.

The environment variables button is located after the startup and recovery section. In the Environment Variables interface, add a "System variable" at the lower half. Select "new".

-				20. 1		
En	10111	ากา	ent	Vari	iabi	85

Variable	Value
OneDrive	
OneDriveCommercial	
Path	
TEMP	
TMP	
	New Tells
	New Edit Delete
stem variables	
/ariable	Value
ComSpec	C:\windows\system32\cmd.exe
DriverData	C:\Windows\System32\Drivers\DriverData
GIT_LFS_PATH	C:\Program Files\Git LFS
NUMBER_OF_PROCESSORS	8
OS	Windows_NT
Path	C:\ProgramData\DockerDesktop\version-bin;C:\Program Files\D
PATHEXT	.COM;:EXE;:BAT;.CMD;:VBS;:VBE;:JS;:JSE;:WSF;:WSH;:MSC
	AMD64
PROCESSOR ARCHITECTURE	
PROCESSOR ARCHITECTURE	New Edit Delete
PROCESSOR ARCHITECTURE	New Edit Delete

×

Figure 6. The environment variables interface.

The user must select the "New" button in the System Variables section in order to add a new system variable.

Finally, the user must set the variable name to 'JDK8_HOME' and the variable value to the folder where the user installed JDK 8 (example: C:\Program Files\Java\jdk1.8.0_151). The user must name the Java variable, "JDK8_HOME." The variable value is wherever the user installed Java 8.

Variable name:	JDK8_HOME		
/ariable value:	C:\Program Files\Java\jdk1.8.0_151		

Figure 7. The new system variable interface.

20

Using multiple versions of Java

JDK 8 is required to launch the CTS. As there might be multiple installations of different versions of Java on a user's system, it is in the user's best interest to set an interchangeable environment variable on their machine. The manipulation of the environment variable allows multiple versions of Java to exist together and the user to switch between them. The user must name the variable, "JAVA_HOME." The variable references another system variable. In this case, Java 8.

Create a SYSTEM level environment variable JAVA_HOME set to the value: %JDK8_HOME%.

New System Variable			\times
Variable name:	JAVA_HOME		
Variable value:	%JDK8_HOME%		
Browse Directory	Browse File	OK Cancel	

Figure 8. The environment variables dialogue.

The user must add "%JAVA_HOME%\bin" to the path and move it to the top of the list. The result is shown in below figure, and outlined in red.



X

Figure 9. The PATH variable dialogue, with the JAVA_HOME environment variable outlined in red.

MSYS2 (for C/C++/Ada samples only)

MSYS2 is a development environment that provides better interoperability between Unix-like installations with native Windows software. The CTS depends on POSIX to process C/C++/Ada applications, and Windows does not include POSIX. Thus, MSYS2 is required for the CTS to run on a Windows operating system.

If the user is operating a 32-bit architecture, download MSYS2 from https://www.msys2.org/ . Download the "msys2-i686" executable. If the user is operating a 64-bit architecture and would like to install from the official website rather than the CTS-provided installers, download the "msysx86_64" executable.

After obtaining the executable, run the executable. Follow the prompts. The installation directory must be "C:\msys64," which is the path the CTS looks for when executed.

After installing, open a MSYS2 MINGW 64-bit terminal (or 32-bit, depending on the user's machine) by pressing the start key and searching for "mingw." The application should be at the top of the start menu.

In the terminal, update the package database and core system packages.

pacman -Syu

If needed, close the terminal and launch the terminal again. The user can finish updating the package database and core system packages by executing:

pacman -Su

If there are additional problems with the initial MSYS2 installation, it is recommended to consult the MSYS2 detailed installation guide at https://github.com/msys2/msys2/wiki/MSYS2-installation.

Install several additional required packages via pacman:

pacman -S mingw-w64-x86_64-toolchain base-devel msys2-devel make

The user will be prompted to select configuration for the packages that pacman was asked to install. Select "default - install all," and confirm with "Y".

Open file "C:\msys64\msys2_shell.cmd" and edit line "rem set MSYS2_PATH_TYPE=inherit" by removing 'rem', which will look like the following when done:

set MSYS2_PATH_TYPE=inherit

The same way that an environment variable was added to the path in Java 8, and Python 2.7 installations, the user must add MSYS2 to their environment's path. MSYS2's environment variable also must be near the top. The user must set **both** "C:\msys64\mingw64\bin" and "C:\msys64\usr\bin" as environment variables.

IMPORTANT

For the CTS to work correctly, MSYS2 directories should *NOT* be listed before Python 2.7 directories in the environment path.



×

Figure 10. The msys64 path declarations, with variables are outlined in red.

Lastly, the user needs to remove the libdep.a from their MSYS2 installation directory to avoid ar.exe error **0xc000012f** caused by libdep.a.





```
rm C:\msys64\mingw64\lib\bfd-plugins\libdep.a
```

Ant 1.9.x

Download the Ant binary distribution zip file from https://ant.apache.org/bindownload.cgi. Extract the "apache-ant-1.9.9-bin.zip" file to "C:\Program Files\". Ant is precompiled so no installer needs to be run to have Ant properly work.

Next, the user must create a SYSTEM level environment variable ANT_HOME set to the folder where the user installed Ant 1.9.9 (example: C:\Program Files\apache-ant-1.9.9).

/ariable name:	ANT_HOME			
Variable value:	C:\Program Files\apache-ant-1.9.9			

Figure 12. Ant environment variable.



Figure 13. Pointing the system path to the relevant Ant directories, with the variables are outlined in red.

Finally, the user must add "%ANT_HOME%" and "%ANT_HOME\bin% to their SYSTEM-level PATH variable, near the top.

Enable Long Paths in Windows 10

The maximum length for a path on Windows is MAX_PATH which is defined as 260 characters. Starting in Windows 10 version 1607, changing a registry key or using the Group Policy tool is used to remove the limit.

For more information on the long path limitation in Windows, seeNOTEhttps://learn.microsoft.com/en-us/windows/win32/fileio/maximum-file-path-
limitation.

To change registry key:

- 1. From the start menu launch "regedit".
- $2. \ Navigate \ to \ HKEY_LOCAL_MACHINE \ SYSTEM \ CurrentControlSet \ Control \ FileSystem.$
- 3. Set the registry key LongPathsEnabled (Type: REG_DWORD) to 1.

To use the Group Policy too:

- 1. Open Group Policy Editor (Press Windows Key and type gpedit.msc and hit Enter key.
- 2. Navigate to the following directory: Local Computer Policy > Computer Configuration > Administrative Templates > System > Filesystem > NTFS.
- 3. Click Enable NTFS long paths option and enable it.

2.3.5. Installation of CTS

To install the CTS, simply extract the archive file (zip or tar.gz) to a folder where the user has read/write/executable access.

It is recommended to extract CTS close to the root of a drive such as "C:/FACEConformanceTestSuite_x.x.x" or "D:/FACEConformanceTestSuite_x.x.x" in NOTE order to minimize the folder path length. This will help reduce runtime failures resulting from path length and cmd.exe command character length limitations on Windows.

Installation Variance for Windows Cygwin/GCC Toolchains

To test an Operating System Segment UoC that provides a Cygwin GCC C/C++ toolchain hosted on Windows for conformance please use the installation variance as described below.

- 1. Remove MSYS2 from the PATH environment variable.
 - C:\msys64\mingw64\bin
 - C:\msys64\usr\bin
- 2. Add Cygwin as bundled in the product to the PATH environment variable.

%CYGHOME%\bin, where %CYGHOME% is the full path to the root Cygwin directory.

Start CTS from the command line, rather than the installed desktop icon that invokes an MSYS2 shell script. The instructions are documented in Test Suite Command Line Options section of this document.

2.3.6. Running CTS

The user can start the CTS by running the run_CTS_GUI.py script in the root directory of their CTS installation using Windows Command Prompt. Please note that CTS cannot run successfully on powershell or a MSYS2 MINGW terminal.

```
python run_CTS_GUI.py
```

This will launch the conformance main menu as shown in below figure.

File	Run	Help			$\mathbf{\hat{a}}$					
Future A	irborne Capabili	ly Environment*		ne to FACE Conformance Test Suite FACE Technical Standard Edition 3.0						
Re	cent P	rojects		Quick Start						
	No Recent Projects			Run Conformance Test						
				Create a Project Configuration						
									Create a Toolchain Configuration	
			ects	🛞 Preferences						
				Coumentation						

Figure 14. The CTS home screen.

3. Theory of Operation

For C, C++, and Ada code, conformance is determined by integrating targeted testing code with corresponding conformant test code. User applications will be linked with FACE test interfaces. Customer interface libraries will be linked against by FACE test applications. The test interfaces provide all possible function calls, data types, and constants available to the customer code. The test applications utilize all possible function calls, data types, and constants that should exist in the customer code. The test applications are compiled using the customer's header files or spec files (for C/C++/Ada) and then linked against both the customer's code and the test libraries that contain the function calls, data types, and constants allowed by the FACE Technical Standard for a given OS Profile. If the compile and link pass, the customer code is not conformant with respect to the requirements tested. If the compile or link fail, the customer code is not conformant. Errors are included in the test output.



Figure 15. Linked source code interfaces matching and not matching the FACE Technical Standard.

The test only determines conformance with respect to function signature. The test neither proves nor disproves correctness of functionality. Additionally, for testing the existence of abstract interfaces, the test does not determine if the customer code implements the interface, only that the abstract interface is defined correctly in the customer's headers or spec files. For testing existence of non-abstract interfaces, the test determines if the interface is defined in the customer code. For testing use of non-abstract interfaces, the test determines if the interface used by the supplier's code is an allowed interface. It will only pass if that interface is allowed either as an interface defined by the FACE Technical Standard, or allowed per the FACE OS Profile.

3.1. Introduction to Methodology

Two methods of performing the link test exist. One uses the target linker. The other uses the host linker. The target linker is the linker used to produce an executable targeting the embedded system. The host linker is the linker used to produce an executable targeting the development system

where the CTS runs. Each method has its own advantages.

The target linker method is advantageous in that a project's existing build infrastructure can be reused during conformance testing. Additionally, any conditionally compiled code based on hardware architecture which is reflected in the compiler and linker will be included in the conformance testing. The disadvantage is that conformance testing authority must know the details of the target linker.

The host linker is advantageous in that its usage details are preselected in the conformance tool. Its disadvantage is that conditionally compiled code based on hardware architecture which is reflected in the compiler and linker may not be included in conformance testing. Additionally, the project's build infrastructure would need to be modified to make use of the host compiler and linker.

Compiler	
Executable:	····
Flags:	
Output Flag:	
Include Paths:	
Linker	
Executable:	
Flags:	
Output Flag:	
Library Paths:	+ X
Archiver	
Executable: Flags:	
output hug.	

Figure 16. The target linker GUI, found in the Toolchain Configuration Builder's Tools tab.

3.2. Target Linker Method

If the user chooses the target linker method, they must provide the conformance tool details about their build tools. The user must provide the path to and name of the compiler, linker, and archiver

for their build tools. Additionally, the user must provide compiler flags, linker flags, and archiver flags to provide correct behavior.

3.3. Host Linker Method

If the user chooses the host linker method, they must alter their project's build system to use the host's build tools and recompile. The user must be mindful of any conditionally compiled code based on architecture or compiler.

3.4. Additional Methodology Information

When the user builds their project, they must alter their compiler flags to include the conformance tool's Gold Standard Libraries (GSL) directory for IOSS, TSS, and OSS headers. Details on how to achieve this is described above in the Target Linker Method section.

3.4.1. OSS Testing Methodology

Unlike the other segments, to test the OSS using CTS, the system libraries and include files will need to be used.

The user will want to specify the language standard, but they will not want to disable the headers and built in functions and libraries. The user will also need to specify the location of include files and libraries to be used in the system test, either by compiler and linker option flags, or by selecting include paths and libraries via the configuration GUI as described in the Testing an Operating System (OSS) Segment section below.

3.4.2. Java Testing Methodology

The Java testing methodology differs greatly from the methodology for C, C++, and Ada. This is due to the standardized data format of Java's .class files allowing these files to be universally queried for information.

PCS and PSS segment class files are queried for their dependencies such as any classes, methods, or fields necessary to execute. These dependencies are compared against a white list as defined by the standard. Violations are reported as errors.

OSS, TSS, and IOSS segment class files are queried for their capabilities such as classes, methods, and fields as well as attributes for each. These are compared against a minimum list as defined by the standard. Any omissions or incorrect definitions are reported as errors. Additionally, native methods are flagged as warnings to inspect.

4. Toolchain Configuration File

4.1. Introduction

A toolchain configuration file (TCFG, .tcfg, toolchain file, toolchain) contains information to configure and compile CTStest objects. A toolchain configuration file also contains information about how to link with a user supplied UoC, given the UoC target environment. This information provides an environment where the CTS can configure the correct environment to use information stored in the Project Configuration file. The toolchain configuration file ending is .tcfg.

Toolchain configuration files are generated with string template (http://www.stringtemplate.org/), a freely available template library for generating source code.

4.2. Toolchain Files List

The Toolchain Files List can be accessed by selecting the File > Toolchains option from the navigation bar.

File Run Help				
🔓 New 🖾 Import 🦰 Open	🕤 Clone 🚺	Remove		
Toolchain Files Directory: /home/cts/De	sktop/dev/CTS3x	/toolchain/configuratio	n_files	Change
Toolchain File	Language	Segment Type	Notes	
C99_NonOSS_General_toolchain.tcfg	C99	Non OSS Toolchain	C99_NonOSS_General_to	olchain.tci
C99_OSS_Safetybase_toolchain.tcfg	C99	OSS Toolchain	C99_OSS_Safetybase_to	olchain.tcf
C++03_NonOSS_General_toolchain.tcfg	CPP03	Non OSS Toolchain	C++03_NonOSS_Genera	l_toolchair

Figure 17. The Toolchain Files List.

The following options are available either by default or when the user selects a toolchain from the list view:

- New Opens the toolchain editor for creation of a new toolchain from scratch.
- **Import** Provides a file browser dialog to allow the user to find and select one or more existing toolchain file(s) and allow it to be copied to the "Toolchain Files Directory" displayed above the list view. (Note that this option is different from the Project Files List's Import function because the user is making a copy of an existing toolchain from another location to the working

directory location. If the user intends on modifying a toolchain that is not located in the working toolchain directory, then it is best to change the working toolchain directory to be that of the directory from which the toolchain resides in.)

- **Open** Opens the currently selected toolchain from the list view into the toolchain editor.
- **Remove** Removes the currently selected toolchain from the list view. (Note that this option does not delete the toolchain, but removes it from the list view only.)
- **Clone** Creates a copy of the currently selected toolchain and saves it to the "Toolchain Files Directory".
- **Change** This opens a directory browser dialog to allow the user to change the directory to search for and display all available toolchains in this toolchain list view.

Further, the user may define a "Toolchain Files Directory", a directory for the CTS to detect TCFG files to automatically import into the toolchain file list.

4.3. Building a Toolchain Configuration File

The subsequent sections detail how to build a toolchain file and what each toolchain option means. To begin, the user must click the "Create a Toolchain Configuration" button on the home page of the GUI.

	C99_NonOSS_General_toolchain.tcfg - Toolchain Configuration _ C ×
File Run Help	← 🏠
Toolchain Configuration	n Builder
📴 Check Configuration	Save 🕌 Save As
	General
General	OS Info: Sys: [Linux], Release: [3.10.0-1160.81.1.el7.x86_64], Version: [#
File Extensions	Language: C99 💌
Tools	Segment Under Test: IOSS/PCS/PSSS/TSS/OSS Config/LCM OSS Non-Config/LCM OSS Profiles: V General Safety Extended Safety Base Security
Compiler Specific	PATH Additions:
Notes	<pre>/usr/bin //usr/bin //</pre>
	Environment Variables Additions:
	+ Name Value
	_ dummy 123
	hello world
Click the report icon to the right	for detailed results

Figure 18. The Toolchain Configuration Builder with the General tab selected.

4.3.1. General Tab

The user must select the programming language the UoCs this toolchain are targeted towards. The language must be the same as the candidate UoC('s) language it was programmed in.

Next, the user must select the type of segment that the toolchain utilized by. The user must select either "IOSS/PCS/PSSS/TSS" or "OSS", as the process for testing for conformance for OSS segments are different.

The user must then define the OSS profile(s) that the candidate UoC(s) satisfy. There may be more than one profile that is supported by a UoC, and the user must select all that are applicable.

The "PATH addition" section allows the user to include any libraries a UoC may need while being built or archived. The user may add file paths that include these library locations. For example, on Linux-based systems if the user has installed gcc, including "/usr/bin", it is required to allow the toolchain to recognize the path of the compiler.

The "Environment Variables Additions" section allows the user to define an environment variable name and value. In the sample projects that are generated by the CTS, the environment variables are "dummy" and "hello" with values "123" and " world," respectively.

4.3.2. File Extensions Tab

	C99_Non	OSS_General_toolchain.tcfg - Toolc	hain Configura	ation _ 🗆	×
File Run Help				~	
Toolchain Configuration	Builder				
📴 Check Configuration	Save 🕻	Save As			
General	File Extens	sions			
General	Header:	h	Object:	0	
File Extensions	Source:	c	Executable:	x	
Tools	Library:	a]		
Compiler Specific					
Notes					
Click the report icon to the right f	or detailed	results			

Figure 19. The Toolchain Configuration Builder with the File Extensions tab selected.

The user must define each of the file extensions that their UoC(s) use:

- Choose the extension of the header/source files. o The extension should be the extension used by the programming language that the segment uses.
- The user may choose the extension used for object files and libraries by the compiler

The user may choose to include the extension used for executable files by the compiler. (Leave blank for no extension.)

4.3.3. Tools Tab

	C99_NonOSS_0	General_toolchain.tcfg - Toolchain Configuration _ 💷 🗄	×
File Run Help		← 🏠	
Toolchain Configuration	n Builder		
Check Configuration	Save 🔏 Save	As	
	Compiler		
General	Executable:	cc	
File Extensions	Flags:	-nostdinc -D_XOPEN_SOURCE=700 -D_USE_SVID -D_GNU_SOURCE -DFACE_GE	
Tools	Output Flag: Include Paths:	-o +	
Compiler Specific		\$	
Notes			
	Linker		
	Executable: Flags: Output Flag: Library Paths:	gccnodefaultlibs -nostartfiles -00 -o	
Click the report icon to the right	for detailed results	- I I I I I I I I I I I I I I I I I I I	a)

Figure 20. The Toolchain Configuration Builder: Compiler Options on the Tools tab.

The user has a choice on which compiler they want to use to test their UoC(s), which must be defined in the toolchain configuration file.

The "Compiler" section allows for the user to define the compiler executable needed to invoke the compiler to build, execute, and archive. As described in the Theory of Operation, the user has the option of testing a UoC using a target or host toolchain. According to their choice, the user might define the toolchain configuration file differently.

The user must first define the compiler executable in the "Executable" field. It is recommended to specify the exact compiler, not the compiler collection if possible (i.e. g over gcc, if constructing a toolchain for C). Further, the user may click the ellipsis button on the right of the Executable field to provide an absolute path to the compiler.

There are also fields to define processor-specific flags, and an output flags that a UoC might need to successfully compile, link, and archive located below the "Executable" field as shown in the above figure. The flags must instruct the tools to ignore any system included code such as standard headers and libraries. The flags must also select the correct target language standard. Table 8, Table 9, and Table 10 provide the minimum set of equivalences the user must provide. These should be added when using the target linker method.

Table 8 contains flags that are used to let the compiler know what language to compile.

IMPORTANTDue to the nature of how the CTS operates, compiler optimizations should
not be used (e.g., -00 for gcc) when compiling and linking. Otherwise, false
results could be reported.

Table 8. Language standard that the CTS supports for a specific language.

Language	ISO Language Standard	GNU Tools Example
C99	ISO C 1999	-std=c99
C++03	ISO C++ 2003	-std=c++03 (or c++0x on some compilers)
Ada	ISO Ada 1995	-std=-gnat95
Ada	ISO Ada 2012	-std=-gnat12

Table 9. Compiler flags for Non-OSS tests.

Purpose	Flag
disable bundled headers	<pre>-nostdinc (or -nostdinc++)</pre>
disable built-in functions	-fno-builtin

Table 10. Linker flags for Non-OSS tests.

Purpose	Flag
disable Built-in Libraries	-nodefaultlibs -nostartfiles

NOTE For Ada segments, the user can choose a binder to use during the build procedure.

If the user is using a sample NonOSS toolchain for C and C++, the appropriate macro symbol should be defined for the profile chosen as shown in Table 11. This symbol is used by the sample compiler specific "allowed definitions" code and must be set for the associated toolchain files to operate. See Allowed Definitions for more information about "allowed definitions".

Profile	Macro Symbol
General Purpose	-DFACE_GENERAL_PURPOSE_PROFILE
Safety Extended	-DFACE_SAFETY_EXTENDED_PROFILE
Safety Base	-DFACE_SAFETY_BASE_PROFILE
Security	-DFACE_SECURITY_PROFILE

Table 11. The C and C++ Profile Macro Symbols for Sample Allowed Definition.

As a part of the compilation process, UoCs may have external libraries linked to it. The "Linker" section provides an area where the user may use the "Executable" field to produce the linking executable or use the ellipsis button to define an absolute path. The CTS also provides a field to define processor specific flags, an output flag, and specific library paths to be included in the linking process.
	C99_NonOSS_Gener	ral_toolchain.tcfg - Toolchain Configuration		-	• ×
File Run Help			÷		
Toolchain Configuration	n Builder				
Check Configuration	Save 🕌 Save As				
General File Extensions Tools Compiler Specific Notes	Linker Executable: gcc Flags: -no Output Flag: -o Library Paths: + X	defaultlibs -nostartfiles -O0			
	Archiver				
	Executable: ar Flags: cr Output Flag:				
Click the report icon to the right	for detailed results				Ē

Figure 21. The Toolchain Configuration Builder: Linker Options on the Tools tab.

The "Archiver" section allows the user to define an archiver executable to create, modify, or extract code from archives. The CTS provides fields to provide flags to customize exactly how the user's UoC will be archived, as shown in the above figure.

Finally, the user must add a toolchain template file (with file extension .stg) by clicking the ellipsis button. The toolchain template files contain templates that are used to format toolchain-related commands for compilers.

After selecting the template and defining the various toolchain commands/flags above, the user may click the refresh button next to the "Template Output" header in the below figure to show the example commands the CTS will use based on the commands the user has configured and the selected template.

Without the toolchain template file, the toolchain will be invalid. ToolchainNOTE templates for each FACE supported language can be found in the datafiles/stringtemplate folder of the CTS.

	C99_NonOSS_	.General_t	oolchain.tcfg - Toolchain Configuration _		×	
File Run Help			←	6	t	
Toolchain Configuration	n Builder					
📴 Check Configuration	Save 🔏 Save	As				
	Executable:	ar				
General	Flags:	cr				
File Extensions	Output Flag:					
Tools	Toolchain Temp	late				
Compiler Specific	Toolchain Template File /home/cts/Desktop/dev/CTS3x/datafiles/stringtemplate/default					
Complier Specific	Template Ou	tput 💭				
Notes	Compile Command:					
	cc -o EXAMPL -DFACE_GENI	E_SOURCE_ ERAL_PURPO	FILE.o -nostdinc -D_XOPEN_SOURCE=700 -D_USE_SVID -D_GNU_SOUR SE_PROFILE -std=c99 -c -fno-builtin EXAMPLE_SOURCE_FILE.c	CE		
	Link Comman	d:				
gcc EXAMPLE_OBJ1.o EXAMPLE_OBJ2.o -nodefaultlibs -nostartfiles -O0 -o EXAMPLE_TARGET.x						
	Archive Comr	nand:				
	ar cr EXAMPL	E_LIB.a EXA	MPLE_OBJ1.0 EXAMPLE_OBJ2.0			
Click the report icon to the right	for detailed result	S				

Figure 22. The Toolchain Configuration Builder: Toolchain Template on Tools Template tab.

4.3.4. Compiler Specific Tab

Compiler Specific Functionality

There is compiler specific information that will be needed to conduct conformance tests. The "Compiler Specific" tab allows the user to further define compiler parameters needed to successfully test a UoC within the CTS. This information is stored in the compilerSpecific subdirectory.

In particular, the mapping between standard types in C/C++ and their exact definitions for a given compiler will need to be specified. There may also be compiler specific built-in functions/methods that cause linker errors even when compiler and linking against the OS gold standard libraries (i.e. *main*, stack_chk_fail). There may be valid graphics related calls that are not called out specifically in the standard.

You may add allowed functions to the conformance test by editing the "CompilerSpecific" source file. This file can be edited in the Compiler Specific section of the toolchain configuration builder. You only need to add a function stub, since these conformance test objects are never actually executed. The compiler specific source file is included in the conformance report to show any functions that were used.

To specify the language mappings, the exact types need to be added to the toolchain file.

Compiler specific methods must be reported to the Verification Authority (VA) (and are included in the Test Suite results).

Configuration

Exact Types:

For C and C++ testing, the exact size types must be configured according to the user's target OS. This is done through the Compiler Specific tab. The user must consult their compiler's system definitions to get the operating system's defined intrinsic types. The user must then add the intrinsic types in their respective fields to create a typedef mapping between the intrinsic type and FACE exact type needed for testing.

Note: Mapping exact types is not required if the toolchain is intended for Ada or Java.

	C99_NonOSS_	General_toolchain.tcfg - Toolchain Configuration	-		×
File Run Help		<	-	ľ	
Toolchain Configuration	n Builder				
Provide the configuration	Save 🔏 Save	As			
	Exact Types Defi	nitions			
General	FACE_int8_t	char			
	FACE_int16_t	short int			
	FACE_int32_t	int			
Tools	FACE_uint8_t	unsigned char			
	FACE_uint16_t	unsigned short int			
Compiler Specific	FACE_uint32_t	unsigned int			
	FACE_size_t	long unsigned int			
Notes	✓ Supports 64	bit			
	FACE_int64_t	long int			
	FACE_uint64_t	unsigned long int			
	NULL Definition				
	#ifdefcplus; // Define f #define F #else // Define f #define F #endif	olus NULL for C++ as the constant 0 with no specific type. IACE_NULL 0 NULL for C as 0 cast to a void pointer. IACE_NULL ((void*) 0)			
Click the report icon to the right	for detailed results				

Figure 23. The Toolchain Configuration Builder, with the Compiler Specific tab selected.

Exact Type	Description
FACE_int8_t	8-bit signed integer
FACE_int16_t	16-bit signed integer
FACE_int32_t	32-bit signed integer
FACE_int64_t	64-bit signed integer
FACE_uint8_t	8-bit unsigned integer
FACE_uint16_t	16-bit unsigned integer
FACE_uint32_t	32-bit unsigned integer
FACE_uint64_t	64-bit unsigned integer
FACE_size_t	Unsigned integer type of the result of sizeof()

Table 12. The list of intrinsic types that map to FACE's exact types.

Null Definition:

In the "NULL Definition" section, the user must define what NULL means for their target operating system, as compilers may define NULL differently. The NULL type must be configured according to the system-defined value for "NULL". This may be done by entering the null TYPES in the null definition, shown in below figure.

	C99_NonOSS_General_toolchain.tcfg - Toolchain Configuration	-	•	ĸ
File Run Help	←			
Toolchain Configuration	n Builder			
📴 Check Configuration	Save Save As			
General	NULL Definition			
File Extensions	<pre>#ifdefcplusplus // Define NULL for C++ as the constant 0 with no specific type. #define FACE_NULL 0 #else // Define NULL for C or 0 contact to quark the states.</pre>			
Tools	#define FACE_NULL ((void*) 0) #endif			
Compiler Specific				
Notes	Allowed Definitions			l
	+ Allowed Definition 0			
	OpenGL Definition			
	✓ OpenGL			
Click the report icon to the right	for detailed results			4

Figure 24. The Toolchain Configuration Builder with the Compiler Specific tab selected.

The user may add allowed definitions in the "Allowed Definitions" section, shown in the below figure. By adding an allowed definition, the user lets the compiler know what the UoC uses outside of the OSS's boundaries. By default, an allowed definition must define an entry point. For example, if the UoC the toolchain is intended for is an IOSS or TSS, the user must define device driver calls as an allowed definition. Furthermore, there may also be compiler specific built-in functions/methods that cause linker errors even when compiling and linking against the OS GSL (i.e. *main*, stack_chk_fail) that the user must add as an allowed definition. When a UoC is compiled and linked, the allowed definitions must be included.

Allowed Definitions:

To write an allowed definition, the user needs to add a function stub and a simple function body, since these conformance test objects are never actually executed. This allows for the link test to return with errors. An example of an allowed definition is shown in the below figure. The compiler specific source file is also included in the conformance report to show any functions that were used. Compiler specific methods must be reported to the Verification Authority (VA) (and are included in the CTS results).

There may be valid graphics related calls that are not called out specifically in the Technical

Standard. If the user is creating a UoC with a graphical component, the user must utilize the "OpenGL Definition" section by checking the "OpenGL" checkbox. Then, the user must select what version(s) of OpenGL they are using and link the EGL API, GL2 API, and KHR API platform header files. These headers define specific function declarations and type definitions for the CTS's use for testing graphical interfaces within the UoC(s).

To add an allowed definition, the user must click the "" button on the left of the allowed definitions pane. When the "" is pressed, the user can write definitions directly within the CTS. The user must add the code to the header and source tabs by editing the text area.



Figure 25. The Allowed Definition editor.

4.3.5. Notes Tab

The user has the ability, if needed, to take unique notes on a certain toolchain. This allows the user to quickly notate specific functionality that the toolchain contains and is shown to the user on the main "Toolchain File List" interface, in the far-right column.

	C99_NonOSS_General_toolchain.tcfg - Toolchain Configuration	-	o x
File Run Help	←		
Toolchain Configurati	on Builder		
Check Configuration	Save Save As		
General File Extensions Tools Compiler Specific Notes	Notes C99_NonOSS_General_toolchain.tcfgtemplate: Example Toolchain Configuration for NonOSS segment(s) and general profile	. C99 u	ising
Click the report icon to the rigl	ht for detailed results		Ē

Figure 26. The Project Configuration Builder with the Notes tab selected.

5. Project Configuration File

5.1. Introduction

The project configuration file contains all UoC object paths, dependencies, and settings in order to accurately test a UoC for conformance within the CTS. By defining a project configuration file within the CTS, a .pcfg file is created with the user's selected options. This .pcfg file is used by other tools contained in the CTS to test a UoC for conformance.

5.2. Project Files List

The Project Files List can be accessed by selecting the File from the navigation bar, and "Projects" from the dropdown.

Proje	ect Files List - F	ACE Conforman	ce Test Suite 3.1	.5 –	o x
File Run Help				~	
🔒 New 🙆 Import 🦰 Open 🥤	Remove	🕤 Clone 🜔	Test Project		
Project File	Segment	Language	Profile	Last Modified	Note
C_TSS_Safetybase_CSP.pcfg	TSS	C99	SAFETY_BASE	May 02, 2023 04:42:37 PM	
CPP_TSS_Safetyext_TSTAAdapter_cpp0	TSS	CPP03	SAFETY_EXT	May 02, 2023 04:42:37 PM	
Ada_PCS_Safetybase.pcfg	PCS	ADA	SAFETY_BASE	May 02, 2023 04:42:36 PM	
C_PSSS_General.pcfg	PSS	C99	GENERAL	May 02, 2023 04:42:37 PM	
CPP_PCS_Safetybase_LCM_cpp03.pcfg	PCS	CPP03	SAFETY_BASE	May 02, 2023 04:42:37 PM	
C_OSS_C99.pcfg	OSS	C99	GENERAL	May 02, 2023 04:42:37 PM	
Java_TSS_General_TPM.pcfg	TSS	JAVA	GENERAL	May 02, 2023 04:42:37 PM	

Figure 27. The Project Files List.

This view represents a working sandbox view of project files that have been created or recently edited. Selecting a project from this list view will provide access to the following options:

- New Opens a new file dialog to create an empty project from scratch.
- **Import** Provides a file browser dialog to allow the user to find an existing project file and allow it to be added to the list view.
- **Open** Opens the currently selected project from the list view.
- **Remove** Removes the currently selected project from the list view. (Note that this option does not delete the project but removes it from the list view only)

- **Clone** Creates a copy of the currently selected project and saves it at the same location as the original
- **Test Project** Executes the test procedure on the currently selected project.

5.3. Building a Project Configuration File

The following subsections detail each option available to the user in the Project Configuration builder. Sections 7.2 and 7.3 explain how to set the project configuration file for a specific UoC type (PCS, PSSS, TSS, IOSS, and OSS) through the CTS. Unlike toolchain configuration files, one project configuration file is defined for every FACE UoC.

Upon opening a project configuration file within the CTS, the user will see the Project Configuration Builder interface.

MyNewProject.pcfg - Project Configuration × File Run Help ← 仚 Project Configuration Builder -2 索 ы General General Base Directory: /home/cts/CTSProjects PCS Segment: Data Model C99 Ŧ Language: Ŧ General Profile: Gold Standard Libraries Operating Environment: POSIX -Objects/Libraries Use Multi Process APIs POSIX Multi Process: ARINC653 Part 1 Version: OpenGL: None -Notes Choose A Toolchain Toolchain: ... + Project Info UoC Name: Type UoC Name Click the report icon to the right for detailed results...

5.3.1. General Tab

Figure 28. The Project Configuration Builder with the General tab selected.

For project configuration files to construct file paths, the user must define a base directory in the "Base Directory" field. All files that are then selected within the project configuration file containing a relative path to the absolute file, based on this base directory. For example, if the user declared their base directory to be "/home/user/CTS," and decided wanted to select a toolchain file located at /home/user/CTS/test-toolchain.tcfg, the toolchain path will be just "test-toolchain.tcfg."

The user must then select the FACE UoC segment the UoC is (PCS, PSS, TSS, IOS, OSS), the language the UoC is programmed in, and OSS profile that the UoC reflects.

In FACE UoC development, the operating environment must be defined. The user must select the environment for which the UoC is targeted to operate. There are options for POSIX, ARINC653, and POSIX ARINC653.

- ARINC 653: For an OSS UoC providing ARINC 653 APIs, this indicates the UoC provides all the required ARINC 653 APIs for the selected profile in the FACE Technical Standard 3.0 (further inputs are required in the Objects/Libraries tab as described later). For all other UoCs, this indicates the UoC may use any of those ARINC 653 APIs provided by another OSS UoC as required by the standard.
- **POSIX**: For an OSS UoC providing POSIX APIs, this indicates the UoC provides all the required POSIX APIs for the selected profile in the FACE Technical Standard 3.0 (further inputs are required in the Objects/Libraries tab as described later). For all other UoCs, this indicates the UoC may use any of those POSIX APIs provided by another OSS UoC as required by the standard.
- POSIX ARINC 653: For an OSS UoC providing POSIX and ARINC 653 APIs, this indicates the UoC provides all the required POSIX APIs for the selected profile in the FACE Technical Standard 3.0, and the subset of required ARINC 653 APIs that an OSS UoC in a POSIX environment can provide as defined in the FACE Technical Standard, Edition 3.0 (further inputs are required in the Objects/Libraries tab as described later). For all other UoCs, this indicates the UoC may use any of those POSIX APIs or the subset of ARINC 653 APIs provided by another OSS UoC in a POSIX environment as required by the standard.

For an OSS UoC the POSIX Multi Process APIs can all be tested per the FACE Technical Standard 3.0 if the Use Multi Process APIs checkbox is selected. For other segments this Use Multi Process APIs checkbox, if checked, will indicate that the UoC may use these APIs.

If the user has selected ARINC653 or POSIX ARINC653 as their target operating environment, the "ARINC653 Part 1 Version" options will be available for selection. This defines which ARINC 653 version the UoC is targeted towards.

The user has the option to select what OpenGL APIs the UoC uses, if at all.

The user must input the toolchain configuration file the candidate UoC must be compiled with. Toolchain Configuration Files contain more information about toolchain configuration files. The user may either use an existing or sample toolchain file, or create a new toolchain configuration by following the procedure from the Toolchain Configurations Files section.

Finally a UoP name must be set and this name must match the name given to it in the data model they will be using for PCS and PSSS UoCs.

5.3.2. Data Model Tab

	UntitledProject.pcfg - Project Configuration	_ 0 ×
File Run Help		←
Project Configuration	Builder	
		* ا
	Data Model	
General	Shared Data Model:	
Data Model	LIDP Supplied Model	
Gold Standard Libraries	Entity Uniqueness Observable Uniqueness	
Objects/Libraries	UoP: Choose a UoP	Ŧ
Notes	Associated Views:	
Project Info		
Click the report icon to the righ	t for detailed results	8

Figure 29. The Project Configuration Builder with the Data Model tab selected.

The Data Model tab allows the user to provide the location of the SDM and USM. The ellipses buttons at the right of each input field allows the user to provide an absolute path via file dialogue.

In case the user decided to define every entity as unique in their USM, they must check "Entity Uniqueness" under the USM field. If the user decided to define every observable as unique in the USM, they must check "Observable Uniqueness" under the USM field.

Finally, the user may select which PCS or PSSS UoC model element corresponds to the UoC under test. The dropdown list will be automatically populated when a valid USM is entered in the USM field. Once a model element is selected, the "Associated Connections" text box will automatically populate with the relevant views for that UoC.

5.3.3. Gold Standard Libraries Tab

The GSL tab allows the user to specify the location the GSLs will be generated.

	UntitledProject.pcfg - Project Configuration	_ • ×
File Run Help		← 🏠
Project Configuration	Builder	
		* ا
	Gold Standard Libraries	
General	GSL Directory: /	
Data Model		
Gold Standard Libraries		
Objects/Libraries		
Notes		
Project Info		
Click the report icon to the rig	ht for detailed results	<u>e</u>

Figure 30. The Project Configuration Builder with the Gold Standard Libraries tab selected.

The user must use the ellipses button on the right of the "GSL Directory" field to select a path for the GSLs to be generated.

5.3.4. Objects/Libraries Tab

The Object/Libraries tab allows the user to define a UoC's dependencies, either object file or source code location, and select the FACE Interfaces that a candidate UoC uses/provides.

	UntitledProject.pcfg - Project Configuration	_ 0 ×
File Run Help	(· 🏠
Project Configuration B	uilder	
		۲
	PCS	
General	TypedTS Extended: Uses	
Data Model		
Gold Standard Libraries	+	
Objects/Libraries	Include Paths:	
Notes		
Project Info	×	
	Include Files:	
Click the report icon to the right	for detailed results	<u>e</u>

Figure 31. The Project Configuration Builder with the Objects/Libraries tab selected.

The CTS has no knowledge of how the object files 'include' a header, so the user must define all locations that an invoked header is used from. In the VA process, the user must supply these headers to the VA along with the respective file structure as defined in the project configuration file.

The user must supply both the paths of the directories and the absolute path of the files that must be included for the UoC.

	UntitledProject.pcfg - Project Configuration	- 0	×
File Run Help	÷	1	
Project Configuration Bu	uilder		
			*
General	PCS		
Data Model	Provide Segment Objects/Libraries Objs/Libs:		1
Gold Standard Libraries			
Objects/Libraries	◆		
Notes	Generate Objects/Libraries from source code		
Project Info	Source Files:		
Click the report icon to the right f	or detailed results		

Figure 32. The Project Configuration Builder with the Objects/Libraries tab selected.

As per Target Linker MethodThe user may provide object files for conformance testing. In the "Provide Segment Objects/Libraries" section of the user interface, the user may select the object files for the UoC under test. This section of the Objects/Libraries interface is shown in the above figure. Alternately, the user may choose to provide source files to generate Objects/Libraries from source as explained in Host Linker Method. The section that allows the user to define the location of their source files is show in the below figure.

	UntitledProject.pcfg - Project Configuration	- • ×
File Run Help	←	
Project Configuration I	Builder	
		۵
General	PCS	
Data Model	Generate Objects/Libraries from source code	
Gold Standard Libraries		
Objects/Libraries		
Notes	Include main() for PCS/PSS:	
Project Info	Target Directory:	
	Source file with factory functions for interfaces provided (C/C++/Ada only):	
	Life Cycle Management Interfaces Implemented:	
lick the report icon to the righ	t for detailed results	E

Figure 33. The Project Configuration Builder with the Objects/Libraries tab selected.

The user must specify the absolute path of their concrete implementation of Factory Functions for their UoC. More information about Factory Functions and how the user creates a Factory Functions for specific UoC types can be found in Sections 7.2.1.3 and 7.3.2.1.2.

The user must select any interfaces used in the candidate UoC. It is important to note that there is a difference between a "provided" interface and a "used" interface. If the user provides a "used" interface, the user must supply an injectable for that interface.

	UntitledProject.pcfg - Project Configuration	_ 0 ×
File Run Help	÷	
Project Configuration E	Builder	
		۰
General	PCS	
Data Model	Source file with factory functions for interfaces provided (C/C++/Ada only):	
Gold Standard Libraries	LCM LCM Configurable	
Objects/Libraries	LCM Connectable LCM Stateful	
Notes	Specify LCM Stateful Interface Provided by UoC (only for IOS/TSS) Reported Type Name:	
Project Info	Reported Type UoP Model Name: Request Type Name:	
	Request Type UoP Model Name:	
	FACE Interfaces Used: LCM Initializable	
Click the report icon to the right	for detailed results	

Figure 34. The Project Configuration Builder with the Objects/Libraries tab selected.

The section to define Life Cycle Management (LCM) interface implementations are shown in the above figure if the user supplies an LCM Stateful interface.

- For PCS/PSSS UoCs, the associated datatypes must be modeled in the USM. The CTS will pull those in order to generate the Stateful interface.
- For TSS and IOSS UoCs, since USM is not required, the user must give the CTS information on the LCM Stateful interface via the "Reported Type Name" field, "Reported Type Data Model Name" field, "Request Type Name" field, and the "Request Type Data Model Name" field. Each of the Stateful interfaces provides a mechanism to transition a UoC between states. However, the Reported and Requested types are typically a different list of potential states, thus resulting in two different enumerated datatypes.
 - $\,\circ\,$ The Reported state includes all potential states that a UoC can be in.
 - $\circ~$ The Requested state includes the states that an external agent can request a state change to.

The section to define used FACE Interfaces is shown in the below figure. For used Stateful interfaces, the user must provide the interfaces that the UoC is going to use to transition another UoC.

	UntitledProject.pcfg - Project Configuration	_ ¤ ×
File Run Help		← 🏠
Project Configuration	Builder	
		**
	PCS	
General	FACE Interfaces Used:	
Data Madal	LCM Initializable	
Data Model	LCM Configurable	
	LCM Connectable	
Gold Standard Libraries	Configuration Services	
	TSS Component State Persistance	
Objects/Libraries	Analog I/O Interface	
	ARINC429 I/O Interface	
Notes	ARINC825 I/O Interface	
	Discrete I/O Interface	
Project Info	Generic VO Interface	
	I2C I/O Interface	
	MIL-STD-1553 I/O Interface	
	Precision Synchro I/O Interface	
	Synchro I/O Interface	
	Sorial 1/O Interface	
Click the report icon to the rigl	nt for detailed results	<u>e</u>

Figure 35. The Project Configuration Builder with the Objects/Libraries tab selected.

The section to define used LCM Stateful interfaces is shown in below figure. Here, the user must provide the interfaces that the UoC is going to use to transition another UoC.



Click the report icon to the right for detailed results...

Figure 36. The Project Configuration Builder with the Objects/Libraries tab selected.

5.3.5. Notes Tab

The user may add notes to uniquely identify a certain project configuration. Anything the user writes will show in the Project File List for quick selection.



Figure 37. The Project Configuration Builder with the Notes tab selected.

5.3.6. Project Info Tab

	UntitledProject.pcfg - Project Configuration	_ 🗆 ×
File Run Help	←	6
Project Configuration Bu	uilder	
		*
General	OS Info:	
Data Model	Sys: [Linux], Release: [3.10.0-957.el7.x86_64], Version: [#1 SMP Th 23:39:32 UTC 2018], Arch: [64 bits]	u Nov 8
Gold Standard Libraries		
Objects/Libraries	Project Directory:	
Notes	,	
Project Info		
Click the report icon to the right f	or detailed results	B

Figure 38. The Project Configuration Builder with the Project Info tab selected.

The Project Info tab provides information about the project configuration file that has been defined in other sections of the Project Configuration Builder. The user cannot edit any of these sections, rather, they may edit other sections. Changes in other sections are reflected in the overall project. The above figure shows the Project Info tab for the Project Configuration Builder that does not have any options selected, and thus does not have any project information except the detected OS version.

6. Sample Project and Toolchain Configuration Files

Optionally, the user may generate CTS-provided sample projects and generate toolchain files using an included python script. These must be generated using the testUtility.py script, found in the [root directory of CTS]/sample directory.

Sample projects and toolchains are provided for each FACE segment.

- For TSS segments, the UoC name is assumed to be "UOPName."
- For IOSS segments, the UoC name is assumed to be "UOPName."
- For PCS, the UoP name is taken from the sample data model and is set to "UoP1"
- For PSSS, the UoP name is "UoP2" (also per the sample data model).

Folders under the 'sample' directory are as follows:

- projects contains sample projects for all languages.
- toolchains sample toolchains.
- datamodels sample data model used by sample projects.

6.1. Build Flags

Generating all samples at once may not be feasible for the user. Luckily, the testUtility.py script allows for flags that delimit sample generation based on language, profile, FACE segment, and others.

To avoid longer build times, it is recommended that the user may want to set their build flags to build one language at a time ("-c", "-p", "-a", and "-j").

Flag	Usage
-h,help	Shows the help message and lists all possible flags.
-w,windows	Running this script on Windows
-a,ada	Enables Ada
-c,c	Enable C99
-р,срр	Enable C++03
-j,java	Enable Java
-y,pcs	Generate PCS Test
-s,psss	Generate PSSS Test
-t,tss	Generate TSS Test
-i,ios	Generate IOSS Test
-0,0SS	Generate OSS Test
general	Generate General Purpose OS Segment Profile

Table 13. A list of all possible flags in executing the testUtility.py script.

Flag	Usage
safety_base	Generate Safety Base OS Segment Profile
safety_ext	Generate Safety Extended OS Segment Profile
security	Generate Security OS Segment Profile
-e,projects	Generate project (PCFG) files from all PCFG templates found in each language directory
-l,toolchains	Generate toolchain files and generate toolchain-related files from all TCFG templates found in each language directory
-g,build_gsls	Build all GSLs (Gold Standard Libraries) for each enabled language into build_GSL subdir of tests/uops/[lang] (only necessary for running OSS project files which reference the GSLs in this directory)
-u,build_uocs	Build UoPs/UoCs for each enabled language
-r,run	Run all project (PCFG) files in each language directory
-q,quick	Run stepsprojects,build_uocs, andrun for enabled languages
-n,gen_only	Runs stepsprojects,toolchains,build_gsls, andbuild_uocs for enabled languages

These flags may be mixed and matched. For example, if the user chooses to generate C and C++ for profiles General and Security, the user can use the below command to build C/C++ samples and generated files for the profiles General/Security samples:

python testUtility.py --gen_only -cp --general --security

6.2. Linux Generation

Navigate to the top-level directory of CTS. Then, navigate to the "sample" subdirectory:

cd sample

NOTE

If the user chooses to generate sample tests for all provided languages (C, C++, Ada, and Java) they can use the below command to generate all samples project configuration files, toolchain configuration files, gold standard libraries, and build the generated UoCs:

python testUtility.py --gen_only

Users should expect longer time to generate all the possible project & toolchain configurations.

6.3. Windows Generation

Set the JAVA_HOME variable to JDK 8 in order to be able to build the Java sample projects.

export JAVA_HOME=\$JDK8_HOME

(This is not required if only the C/C++/Ada samples will be generated).

IMPORTANT: Open a Windows command prompt. All sample generation must be in the Windows command prompt.

Navigate to the top-level directory of CTS. Then, navigate to the "sample" subdirectory:

cd C:\CTS\conformancetestsuite\sample

If the user chooses to generate sample tests for all provided languages (C, C++, Ada, and Java) they can use this command to build all samples and generated files for the samples:

python testUtility.py --gen_only

WARNING: Generating all sample project and toolchain configurations will take a long time (about 2.5 hours). The user should use at their own discretion.

A successful generation of the samples will result in no errors from the generation logs and populated folders under the 'sample' directory:

- projects contains sample projects for all languages. Source code for C/C++/Ada is stored alongside the project.
- toolchains sample toolchains.
- datamodels sample data model used by sample projects.

NOTE The testUtility.py script generates project files for the CTS (files with extension .pcfg) from templates. These templates are not native CTS projects. They are used only for the sample projects, since the project file requires an absolute path as the base directory for the project. The testUtility.py script generates the project files using the user's system's path to the CTS. The template files (files with extension .pcfgtemplate) are not complete CTS files and cannot be opened with the CTS GUI.

The samples provided are configured for a GCC / GNAT based toolchain. In order to use a different toolchain, modify toolchain configuration template file (files with extension .tcfgtemplate) for the desired language with a text editor. Then, rerun testUtility.py with "-e -l" flags to regenerate the toolchain configurations:

On Windows:

python testUtility.py --gen_only -e -l

On Linux:

```
python testUtility.py --gen_only -e -l
```

There are some sample OSS projects that are included with Linux but are not included with the Windows distribution. This difference is some of the sample OSS projects (C and C++) for Windows fails due to MINGW not being FACE conformant.

6.3.1. Regarding Failing Test Results and Shared Data Model

Part of the full conformance test is a test of the data model provided by the project, where applicable. Part of the data model test involves testing of the SDM, which is not included in the CTS distribution. Therefore, for all sample projects, the USM is used for both the USM and SDM. Because of this, the SDM portion of the data model test will fail. Since the data model test fails, the overall test result is marked as failed in the test report and the CTS. However, if the user examines the report, they can that see the rest of the test results are shown separately as PASS.

For the sample projects, the expected result is PASS for all sample projects except for the C_OSS_POSIX.pcfg and

CPP_OSS_CPP03.pcfg tests on Linux and all the C and C++ OSS tests on Windows. (This is because both Linux and Windows are not FACE Conformant).

7. Testing a UoC

7.1. Overview

A high-level overview of the steps a user will follow to test a UoC is as follows:

- 1. Create the data model (USM) for your UoC (if your UoC uses or provides any type-specific interface the TSS Type Specific or Life Cycle Management (LCM) Stateful interfaces).
- 2. Create a toolchain for your specific compiler/linker/archiver tools, either from scratch or basing it off one of the sample toolchains. The sample toolchains can also be used directly if desired. The toolchain information is saved in a toolchain configuration file (.tcfg).
- 3. Create a basic project by specifying the profile, segment, interfaces the UoC implementation and interfaces it uses, and the data model (if appropriate). The projection information is saved in a project configuration file (.pfcg).
- 4. Run the "Generate GSLs/Interface" button in the toolbar. This will generate all the interface headers (C/C++) / Ada spec files / Java files for the interface that UoC can access or will implement. These files will be placed into a subfolder of the folder specified in the project as the "Gold Standard" folder (the relative path of the subfolder is include/FACE). This process also generates a text file in this location with all the include paths the user should use to compile their code for conformance.
- 5. The user writes their implementation code that implements each interface being provided by the UoC from these generated interfaces created in the previous step. For example, for C++ and Java, the implementation is a derived class for each interface being provided. The base/abstract class is the interface class provided in the Gold Standard subfolder include/FACE as generated by the CTS. For C and Ada, one must create implementations of the functions/procedures. Next, for each FACE interface that the UoC is to "use" (access), the user must also implement the Injectable interface for that interface.
- 6. User compiles their UoC code using the generated headers or spec files or Java files (depending on language) and the include paths (compiler paths or class paths) provided in the generated text file. Alternatively, source files can be provided, and the CTS will build them into object or class files using the toolchain configuration.
- 7. User completes their CTS project configuration by pointing it to the implementation object files (or classes for Java) and runs the CTS.

7.2. Testing a Portable Components Segment (PCS) UoC

The following subsections details instructions to successfully generate a valid project configuration file for a PCS UoC and how to run a test using the Conformance Test Suite. More information about each projection configuration option can be found in the subsections of Project Configuration Files.

7.2.1. What the User Must Provide

The user must provide the following inputs to the CTS:

- The project's object files (C/C++/Ada) or class/jar files (Java). Alternatively, source files can be provided, and the CTS will build them into object or class files using the toolchain configuration.
- The project's header files (C/C++) or spec files (Ada).
- The project's USM.
- The project's toolchain file.

7.2.2. Test Procedures

Providing Project Context

- 1. Successfully install the CTS.
- 2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.



Figure 39. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	roject - FACE Conformance Test Suite 3.0r0-SNAPSHO	r (
Create a New Pro	oject Configuration	
Project Name:	UntitledProject	p
Project Location:	/home/tstittleburg/CTSProjects	
	Ok Canc	el

Figure 40. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.



Figure 41. Project Configuration Builder General tab

- 6. Fill in all options on the General tab for
 - a. Base Directory
 - b. Select "PCS" as segment
 - c. The Language the candidate UoC was written in
 - d. The OSS profile the candidate UoC was intended

- e. The intended operating environment of the UoC
 - i. Enable POSIX multi process APIs if required
 - ii. If ARINC653 or POSIX ARINC653 was selected as the operating environment, select what ARINC653 version is required
- f. If the UoC contains graphics API calls, select from the OpenGL dropdown
- g. Add the targeted toolchain path
- h. Set the UoC name
- 7. Select the Data Model tab to display the data model information below.
 - a. Set the path to the SDM and USM. This directory is relative to the base directory set in the General tab.

CPP_PCS_Safetyext_cpp03.pcfg - Project Configuration				
File Run Help	÷	· 🏠		
Project Configuration E	Builder			
		* ا		
	Data Model			
General	Shared Data Model:////datamodels/surrogate_sdm.face			
Data Model	UoP Supplied Model:////datamodels/model.face			
Gold Standard Libraries	Entity Uniqueness Observable Uniqueness			
Objects/Libraries	UoP: UoP1	•		
Netes	Associated Connections:			
Project Info	UoP1MP1 [PV1, QUEUING_CONNECTION] UoP1MP2 [T1, SINGLE_INSTANCE_MESSAGE_CONNECTION] UoP1CS1 [PV1, T2, ROLE_CLIENT]			
Click the report icon to the right	for detailed results	<u>e</u>		

k the report icon to the right for detailed resu

Figure 42. Data Model tab

- 8. Select the Gold Standard Libraries tab to display the options below.
 - a. Set the directory where the gold standard libraries will be generated and stored for the test.

This directory is relative to the base directory set in the General tab. NOTE

- -	CPP_PCS_Safe	tyext_cpp03.pcfg - Project Configuration	-	o x
File Run Help		(
Project Configuration B	uilder			
)
	Gold Standard Lib	raries		
General	GSL Directory	/home/cts/Deskton/dev/CTS3y/sample/projects/CDD/DCS/Sa	etvext/l	
Data Model	GSE Directory.		eryexu	
Gold Standard Libraries				
Objects/Libraries				
Notes				
Project Info				
Click the report icon to the right	for detailed results.			

Figure 43. Gold Standard Libraries tab

- 9. Select the Objects/Libraries tab to display the portable components options shown below. If a UoC requires one or more of its client connections to be tested using the TS Type-Extended TypedTS interface, check "Uses" the TypedTS Extended. When "Uses" is enabled, each connection checked will generate a TS Type-Extended TypedTS interface in the Gold Standard Library. Otherwise, a separate TypedTS interface will be generated for the given types for each client connection.
- 10. For C/C++ projects, use the list boxes to add the include files and include paths (if applicable) for the concrete interface implementations provided by the UoC. All 'include files' must exist in one of the 'include paths'. Any files included by the concrete implementation of Factory Functions must exist in one of the Include Paths specified. More details about Factory Functions are found in Section 7.2.2.3. More information about all options in the Object/Libraries tab are detailed in Project Configuration Files Obb/Lib tab.
 - a. If the user is providing object files for their UoC, before providing the user's object or library files, they must build them against the Gold Standard Library headers. The CTS will generate the FACE headers for any interface the UoC uses so that the user can build their source code against those. Skip selecting the UoC's object files until the user has generated the GSLs and FACE headers and has built their UoC code against these headers. Therefore, skip the section on selecting object files for now.

	CPP_PCS_Safetyext_cpp03.pcfg - Project Configuration		-	۰	×
File Run Help		←			t
Project Configuration B	uilder				
)	*
	PCS				
General					
Data Model	UoPICS1				
Gold Standard Libraries	±				
Objects/Libraries	Include Paths:				
Notes					
Project Info	Include Files:				
Click the report icon to the right	for detailed results				

Figure 44. Include Paths and Files

11. Scroll down and select any of the FACE Interfaces the UoC implements. If the Life Cycle Management (LCM) Stateful interface is implemented, the datatypes are defined by the architecture model selected.



Figure 45. Life Cycle Management

12. Scroll down and select the FACE Interfaces that are used by the UoC. The UoC must provide an Injectable interface for each FACE Interface it uses. By specifying the candidate UoC "uses" a given interface, it indicates that it implements an Injectable Interface for that interface, and this will be tested by the CTS.



Figure 46. FACE Interfaces Used

- 13. Scroll down and enter the information regarding any FACE Life Cycle Management Stateful interfaces that are used by the UoC. If none are used, leave this section blank. Multiple Life Cycle Management Stateful interfaces may be used by a UoC. The required information for each Stateful interface are:
 - i. the data model and datatype name of the reported datatype
 - ii. the data model and datatype name of the request datatype

	CPP_PCS_Safetyext_cpp03.pcfg - Project Configuration		-		×
File Run Help		←		6	1
Project Configuration Bu	uilder				
)	*
	PCS				
General	LCM Stateful Interfaces Used by UoC				
	Uses LCM Stateful Interfaces				
Data Model					
Gold Standard Libraries					
Objects/Libraries					
Objects/Libraries					
Notes					
	Remove Stateful Interface Used				
Project Info					
	Add New LCM Staterul Interface Used by Uoc				
	Reported Type UoP Model Name:				
	Request Type Name:				
	Request Type UoP Model Name:				
	Add New LCM Stateful Used Interface				
Click the report icon to the right f	or detailed results				

Figure 47. Life Cycle Management Interfaces Used

Generating the Gold Standard Libraries

In order to build the user's source code, the user will need FACE interface headers for any interfaces the UoC uses. For a PCS the user will need any TSS headers the UoC code uses, as standardized in the FACE Technical Standard. The CTS will generate these headers for the user. Click the Generate GSLs Button in the upper left corner of the window as shown below to generate the FACE headers as well as the GSL.



Figure 48. The GSL generation button.

If providing objects for the user's UoC, the user may now build their objects using the FACE headers generated into the GSL directory's 'include/FACE' subdirectory. Examine the contents of this directory to see the standardized header names of all non-OSS FACE Interfaces. Note that for C/C++ all FACE headers should be included with the relative path starting from the FACE directory, for

example: "FACE/IOSS/Analog.hpp" The include directories to be used are described in a generated README file in the GSL directory. OSS include directories are listed and are in specific subfolders of the CTS folder goldStandardLibraries. When the user builds their object code for a UoC, the user will need to include these subfolders and include any FACE headers as "FACE/[name of header file]". (Note that the headers in this subdirectory are deleted each time the test is run, so do not store any project files in this directory.)

The GSL libraries will be generated into the GSL Directory. The user may wish to use the GSLs during development to check that their code builds against them, but there is no need to include them in their CTS project. The CTS will rebuild the appropriate GSLs when the user runs the conformance test and links them as part of the test.

In the "Provide Segment Objects/Libraries" section of the Objects/Libraries tab, the user must enter the full pathnames of the project's object and/or library files. The user may add each object file. The user may also choose the directory where object files are located. All object files in the directory specified as well as object files in subdirectories will be chosen. A combination of directories and object/library files may be specified.



Figure 49. The Project Configuration Builder, with the Objects/Libraries tab selected.

Factory Functions

FACE Interfaces, including Injectable Interfaces, are empty declarations. In order to properly test the user's code against the FACE CTS, the user must provide a file that contains a concrete implementation for each interface needed for the UoC provided. This is called a "Factory Function."

Once the user creates their Factory Function declaration and the user runs the conformance test, a test file declares a pointer to a FACE interface. Then, the CTS instantiates it by calling the Factory Function implementation that the user provided. Once instantiation is complete, it calls each method defined in the interface to ensure complete adherence to the interface.

Generation

To determine which factory functions are necessary, the user must generate the GSL for their project. After generation, the user must find a generated header/spec file named, "CTS_Factory_Functions" in the generated subfolder 'build/GSL/include', which will contain required interfaces.

Providing a Factory Function Implementation

The user must take note of the "CTS_Factory_Functions" file that was generated by the GSLs. The user must provide a file that implements each of these functions. The following paragraphs detail what the user must do per each language the user's UoC implements.

For C/C++, this file (CTS_Factory_Functions .h or .hpp) will contain the declarations of all expected factory functions that the CTS requires for testing the user's UoC. The implementation for each function must instantiate the corresponding concrete class and return a pointer to that object (the return type will be a pointer to the FACE 'abstract' class). Returning a null pointer is not acceptable. This source file must be provided with the user's project and will be reviewed to ensure it instantiates the user's UoC's concrete class for that interface.

For Ada, this will generate a spec file (.ads) cts_factory_functions.ads which has the procedures the user must implement in the source file. The source file for Ada must be named "cts_factory_functions.adb" and implement each of these procedures, returning a concrete version of each type as an access type. In the text field labeled "Source file with factory functions for interfaces provided (C/C++/Ada only)", use the '...' button to the right to browse for the source file. **Any header files included by the source file must exist in one of the Include Paths specified above.**

For Java, a source file named CTS_Factory_Functions.java will be generated in the factory/ subfolder (package subfolder). The user must fill in the implementation of each function, add any imports, and add this to the user's project in the CTS in this file field. Note that this file will NOT be overwritten so if the interfaces the UoC uses have changed, the user must delete their file in order to regenerate a new one with the new set of functions to implement.

Validating and Testing a Project

- 1. Select **1** to verify that the Project Configuration File is valid.
- 2. Click the **()** button at the top of the screen to test the segment. (This may take a few minutes). The results will be written to a PDF file. The directory of the results file will be in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.

7.3. Testing a Platform Specific Services Segment (PSSS) UoC

The following subsections details instructions to successfully generate a valid project configuration file for a PSSS UoC and how to run a test using the Conformance Test Suite. More information about each projection configuration option can be found in the subsections of Project Configuration Files.

7.3.1. What the User Must Provide

The user must provide the following inputs to the CTS:

- The project's object files (C/C++/Ada) or class/jar files (Java). Alternatively, source files can be provided, and the CTS will build them into object or class files using the toolchain configuration.
- The project's header files (C/C++) or spec files (Ada).
- The project's USM.
- The project's toolchain file.

7.3.2. Test Procedures

Providing Project Context

- 1. Successfully install the CTS.
- 2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.



Figure 50. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	roject - FACE Conformance Test Suite 3.0r0-SNAPSHOT 🛛 🗴
Create a New Pr	oject Configuration
Project Name:	UntitledProject .p
Project Location:	/home/tstittleburg/CTSProjects
	Ok Cancel

Figure 51. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.

	*C_PSSS_General_LCM.pcf	g - Project Configuration _	o x
File Run Help		~	
Project Configuration B	uilder		
2			*
Canaral	General		
Data Model	Base Directory: Segment: Language:	/home/cts/Desktop/dev/CTS3x/sample/projects/C PSSS C99	···· •
Gold Standard Libraries	Profile: Operating Environment:	General POSIX ARINC653	* *
Objects/Libraries	POSIX Multi Process:	Use Multi Process APIs	
Notes	ARINC653 Part 1 Version: OpenGL:	2010 None	* *
Project Info	Toolchain: UoC Name:	////toolchains/C99/General/C99_Non() UoP2	+
Click the report icon to the right	for detailed results		Ē

Figure 52. Project Configuration Builder General tab

- 6. Fill in all options on the General tab for
 - a. Base Directory
 - b. Select "PSS" as segment
 - c. The Language the candidate UoC was written in
 - d. The OSS profile the candidate UoC was intended

- e. The intended operating environment of the UoC
 - i. Enable POSIX multi process APIs if required
 - ii. If ARINC653 or POSIX ARINC653 was selected as the operating environment, select what ARINC653 version is required
- f. If the UoC contains graphics API calls, select from the OpenGL dropdown
- g. Add the targeted toolchain path
- h. Set the UoC name
- 7. Select the Data Model tab to display the data model information below.
 - a. Set the path to the SDM and USM. This directory is relative to the base directory set in the General tab.

	C_PSSS_General_LCM.pcfg - Project Configuration			×	
File Run Help	÷				
Project Configuration Bu	uilder				
				8	
General Data Model	Data Model				
	Shared Data Model:///datamodels/surrogate_sdm.face				
	UoP Supplied Model: ././//datamodels/model.face]		
Gold Standard Libraries	Entity Uniqueness Observable Uniqueness			_	
Objects/Libraries	UoP: UoP2		•		
Notes	Associated Connections:				
	UoP2MP1 [PV1, QUEUING_CONNECTION]				
Project Info	UoP2MP2 [T2, SINGLE_INSTANCE_MESSAGE_CONNECTION] UoP2CS1 [PV1, T1, ROLE_CLIENT]				
Click the second ices to the sight f				Ē	

Figure 53. Data Model tab

- 8. Select the Gold Standard Libraries tab to display the options below.
 - a. Set the directory where the gold standard libraries will be generated and stored for the test.

NOTE This directory is relative to the base directory set in the General tab.

	C_PSSS_General_LCM.pcfg - Project C	onfiguration	-	o x
File Run Help		~		
Project Configuration B	ilder			
				*
General	Gold Standard Libraries			
General	GSL Directory: /home/cts/Desktop/de	v/CTS3x/sample/projects/C/PSSS/G	iene	
Data Model				
Gold Standard Libraries				
Objects/Libraries				
Notes				
Project Info				
Click the report icon to the right	or detailed results			

Figure 54. Gold Standard Libraries tab

- 9. Select the Objects/Libraries tab to display the portable components options shown below. If a UoC requires one or more of its client connections to be tested using the TS Type-Extended TypedTS interface, check "Uses" the TypedTS Extended. When "Uses" is enabled, each connection checked will generate a TS Type-Extended TypedTS interface in the Gold Standard Library. Otherwise, a separate TypedTS interface will be generated for the given types for each client connection.
- 10. For C/C++ projects, use the list boxes to add the include files and include paths (if applicable) for the concrete interface implementations provided by the UoC. All 'include files' must exist in one of the 'include paths'. Any files included by the concrete implementation of Factory Functions must exist in one of the Include Paths specified. More details about Factory Functions are found in Section 7.3.2.3. More information about all options in the Object/Libraries tab are detailed in Project Configuration Obj/Lib tab.
 - a. If the user is providing object files for their UoC, before providing the user's object or library files, they must build them against the Gold Standard Library headers. The CTS will generate the FACE headers for any interface the UoC uses so that the user can build their source code against those. Skip selecting the UoC's object files until the user has generated the GSLs and FACE headers and has built their UoC code against these headers. Therefore, skip the section on selecting object files for now.
| | C_PSSS_General_LC | M.pcfg - Project Configuration | - | | × |
|--|--|------------------------------------|---|---|---|
| File Run Help | | ~ | | 6 | |
| Project Configuration E | Builder | | | | |
| | | | | | * |
| General
Data Model
Gold Standard Libraries
Objects/Libraries
Notes
Project Info | PSSS TypedTS Extended: Include Paths: Include Files: | ✓ Uses
✓ UoP2CS1
★
★
★ | | | |
| Click the report icon to the right | for detailed results | | | | |

Figure 55. Include Paths and Files

11. Scroll down and select any of the FACE Interfaces the UoC implements. If the Life Cycle Management (LCM) Stateful interface is implemented, the datatypes are defined by the architecture model selected.



Figure 56. Life Cycle Management

12. Scroll down and select the FACE Interfaces that are used by the UoC. The UoC must provide an Injectable interface for each FACE Interface it uses. By specifying the candidate UoC "uses" a given interface, it indicates that it implements an Injectable Interface for that interface, and this will be tested by the CTS.

	C_PSSS_General_LCM.pcfg - Project Configuration		_ 0 ×				
File Run Help		÷					
Project Configuration I	Builder						
			*				
	PSSS						
General	FACE Interfaces Used:						
	LCM Initializable						
Data Model	LCM Configurable						
	LCM Connectable						
Gold Standard Libraries	Configuration Services						
	✓ TSS Component State Persistance						
Objects/Libraries	Analog I/O Interface						
objects/Libraries	ARINC429 I/O Interface						
	ARINC825 I/O Interface						
Notes	Discrete I/O Interface						
	Generic I/O Interface						
Project Info	I2C I/O Interface						
	MIL-STD-1553 I/O Interface						
	Precision Synchro I/O Interface						
	Synchro I/O Interface						
Click the report icon to the right	t for detailed results						

Figure 57. FACE Interfaces Used

- 13. Scroll down and enter the information regarding any FACE Life Cycle Management Stateful interfaces that are used by the UoC. If none are used, leave this section blank. Multiple Life Cycle Management Stateful interfaces may be used by a UoC. The required information for each Stateful interface are:
 - i. the data model and datatype name of the reported datatype
 - ii. the data model and datatype name of the request datatype

	C_PSSS_General_LCM.pcfg - Project Configuration	-	• ×	
File Run Help	÷			
Project Configuration Bu	uilder			
) *]
General	PSSS			
Data Model	 ✓ Uses LCM Stateful Interfaces Reported: T2 (Data Model: UoPModelName) Request: PV1 (Data Mo 			
Gold Standard Libraries				
Objects/Libraries				
Notes				
Project Info	Remove Stateful Interface Used			1
	Add New LCM Stateful Interface Used by UoC			I
	Reported Type Name:			
Click the report icon to the right f	or detailed results		Ē	Ī

Figure 58. Life Cycle Management Interfaces Used

Generating the Gold Standard Libraries

In order to build the user's source code, the user will need FACE interface headers for any interfaces the UoC uses. For example, for a PCS the user will need any TSS headers the UoC code uses, as standardized in the FACE Technical Standard. The CTS will generate these headers for the user. Click the Generate GSLs Button in the upper left corner of the window as shown below to generate the FACE headers as well as the GSL.



Figure 59. The GSL generation button.

If providing objects for the user's UoC, the user may now build their objects using the FACE headers generated into the GSL directory's 'include/FACE' subdirectory. Examine the contents of this directory to see the standardized header names of all non-OSS FACE Interfaces. Note that for C/C++ all FACE headers should be included with the relative path starting from the FACE directory, for example: "FACE/IOSS/Analog.hpp" The include directories to be used are described in a generated

README file in the GSL directory. OSS include directories are listed and are in specific subfolders of the CTS folder goldStandardLibraries. When the user builds their object code for a UoC, the user will need to include these subfolders and include any FACE headers as "FACE/[name of header file]". (Note that the headers in this subdirectory are deleted each time the test is run, so do not store any project files in this directory.)

The GSL libraries will be generated into the GSL Directory. The user may wish to use the GSLs during development to check that their code builds against them, but there is no need to include them in their CTS project. The CTS will rebuild the appropriate GSLs when the user runs the conformance test and links them as part of the test.

In the "Provide Segment Objects/Libraries" section of the Objects/Libraries tab, the user must enter the full pathnames of the project's object and/or library files. The user may add each object file. The user may also choose the directory where object files are located. All object files in the directory specified as well as object files in subdirectories will be chosen. A combination of directories and object/library files may be specified.



Figure 60. The Project Configuration Builder, with the Objects/Libraries tab selected.

Factory Functions

FACE Interfaces, including Injectable Interfaces, are empty declarations. In order to properly test the user's code against the FACE CTS, the user must provide a file that contains a concrete implementation for each interface needed for the UoC provided. This is called a "Factory Function."

Once the user creates their Factory Function declaration and the user runs the conformance test, a test file declares a pointer to a FACE interface. Then, the CTS instantiates it by calling the Factory Function implementation that the user provided. Once instantiation is complete, it calls each method defined in the interface to ensure complete adherence to the interface.

Generation

To determine which factory functions are necessary, the user must generate the GSL for their project. After generation, the user must find a generated header/spec file named, "CTS_Factory_Functions" in the generated subfolder 'build/GSL/include', which will contain required interfaces.

Providing a Factory Function Implementation

The user must take note of the "CTS_Factory_Functions" file that was generated by the GSLs. The user must provide a file that implements each of these functions. The following paragraphs detail what the user must do per each language the user's UoC implements.

For C/C++, this file (CTS_Factory_Functions .h or .hpp) will contain the declarations of all expected factory functions that the CTS requires for testing the user's UoC. The implementation for each function must instantiate the corresponding concrete class and return a pointer to that object (the return type will be a pointer to the FACE 'abstract' class). Returning a null pointer is not acceptable. This source file must be provided with the user's project and will be reviewed to ensure it instantiates the user's UoC's concrete class for that interface.

For Ada, this will generate a spec file (.ads) cts_factory_functions.ads which has the procedures the user must implement in the source file. The source file for Ada must be named "cts_factory_functions.adb" and implement each of these procedures, returning a concrete version of each type as an access type. In the text field labeled "Source file with factory functions for interfaces provided (C/C++/Ada only)", use the '...' button to the right to browse for the source file. **Any header files included by the source file must exist in one of the Include Paths specified above.**

For Java, a source file named CTS_Factory_Functions.java will be generated in the factory/ subfolder (package subfolder). The user must fill in the implementation of each function, add any imports, and add this to the user's project in the CTS in this file field. Note that this file will NOT be overwritten so if the interfaces the UoC uses have changed, the user must delete their file in order to regenerate a new one with the new set of functions to implement.

Validating and Testing a Project

- 1. Select 📴 to verify that the Project Configuration File is valid.
- 2. Click the **()** button at the top of the screen to test the segment. (This may take a few minutes). The results will be written to a PDF file. The directory of the results file will be in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.

7.4. Testing a Transport Services Segment (TSS) UoC

The following subsections details instructions to successfully generate a valid project configuration file for a TSS UoC and how to run a test using the Conformance Test Suite. More information about each projection configuration option can be found in the subsections of Project Configuration Files.

7.4.1. What the User Must Provide

The user must provide the following inputs to the CTS:

- The project's object files (C/C++/Ada) or class/jar files (Java). Alternatively, source files can be provided, and the CTS will build them into object or class files using the toolchain configuration.
- The project's header files (C/C++) or spec files (Ada).
- The project's USM.
- The project's toolchain file.

7.4.2. Test Procedures

Providing Project Context

- 1. Successfully install the CTS.
- 2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.



Figure 61. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	roject - FACE Conformance Test Suite 3.0rd)-SNAPSHOT
Create a New Pro	ject Configuration	
Project Name:	UntitledProject	
Project Location:	/home/tstittleburg/CTSProjects	
	0	k Cancel
		Curreer

Figure 62. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.

	CPP_TSS_Safetybase_TS.	_cpp03.pcfg - Project Configuration _ I	a x
File Run Help		~	
Project Configuration B	uilder		
			*
	General		
General	Base Directory:	/home/cts/Desktop/dev/CTS3x/sample/projects/CPP/TSS/Safe	
Data Model	Segment:	TSS	· ·
Gold Standard Libraries	Profile:	Safety Base	• •
Objects/Libraries	POSIX Multi Process:	✓ Use Multi Process APIs	
	ARINC653 Part 1 Version:		~
Notes	OpenGL:	None	•
Project Info	Toolchain:		+
	UoC Name:	UOPName	
Click the report icon to the right f	for detailed results		自

Figure 63. Project Configuration Builder General tab

- 6. Fill in all options on the General tab for
 - a. Base Directory
 - b. Select "TSS" as segment
 - c. The Language the candidate UoC was written in
 - d. The OSS profile the candidate UoC was intended
 - e. The intended operating environment of the UoC
 - i. Enable POSIX multi process APIs if required

- ii. If ARINC653 or POSIX ARINC653 was selected as the operating environment, select what ARINC653 version is required
- f. Add the targeted toolchain path
- g. Set the UoC name
- 7. Select the Data Model tab to display the data model information below.
 - a. Set the path to the SDM and USM. This directory is relative to the base directory set in the General tab.

	CPP_TSS_Safetybase_T	S_cpp03.pcfg - Project Configuration _	• ×
File Run Help		~	
Project Configuration Bu	uilder		
) *
	Data Model		
General Data Model	Shared Data Model:	////datamodels/surrogate_sdm.face	
	UoP Supplied Model:	///atamodels/model.face	
Gold Standard Libraries	Entity Uniqueness	Observable Uniqueness	
Objects/Libraries	UoP:	VoP1	
Notes		✓ UoP2	
Project Info	Associated Connections:	UoP1MP1 [PV1, QUEUING_CONNECTION] UoP1MP2 [T1, SINGLE_INSTANCE_MESSAGE_CONNECTION UoP1CS1 [PV1, T2, ROLE_CLIENT] UoP2MP1 [PV1, QUEUING_CONNECTION]	1
Click the report icon to the right fo	or detailed results		Ê

Figure 64. Data Model tab

- 8. Select the Gold Standard Libraries tab to display the options below.
 - a. Set the directory where the gold standard libraries will be generated and stored for the test.
 - **NOTE** This directory is relative to the base directory set in the General tab.

	CPP_TSS_Safetybase_TS_cpp03.pcfg - Project Configuration _		×
File Run Help	÷		
Project Configuration Bu	uilder		
2 🗟 🔏 💾			*
	Gold Standard Libraries		
General	GSL Directory: /home/cts/Desktop/dev/CTS3x/sample/projects/CPP/TSS/Safetybase/TS	S/C	
Data Model			
Gold Standard Libraries			
Objects/Libraries			
Notes			
Project Info			
Click the report icon to the right f	for detailed results		

Figure 65. Gold Standard Libraries tab

- 9. Select the Objects/Libraries tab to display the transport components options shown below. For C/C++ projects, use the list boxes to add the include files and include paths (if applicable) for the concrete interface implementations provided by the UoC. All 'include files' must exist in one of the 'include paths'. Any files included by the concrete implementation of Factory Functions must exist in one of the Include Paths specified. More details about Factory Functions are found in Section 7.4.2.3. More information about all options in the Object/Libraries tab are detailed in Project Configuration Files Obj/Lib tab.
 - a. Select the TSS UoP Type.
 - b. Select the Intra-segment APIs if used.
 - c. If the user is providing object files for their UoC, before providing the user's object or library files, they must build them against the Gold Standard Library headers. The CTS will generate the FACE headers for any interface the UoC uses so that the user can build their source code against those. Skip selecting the UoC's object files until the user has generated the GSLs and FACE headers and has built their UoC code against these headers. Therefore, skip the section on selecting object files for now.

	CPP_TSS_Safetybase	_TS_cpp03.pcfg - Project Configuration		-	o x
File Run Help		•	←		
Project Configuration E	Builder				
					*
	TSS				
General	Type:	TS Interface TSS UoP			•
Data Model	Intra-segment APIs:	Type Abstraction: Uses			
Gold Standard Libraries		Transport Protocol Module: 🗸 Uses			
Objects/Libraries	TS Base: Serialization: Primitive Marshalling:	Uses Implements Uses Implements Uses Implements Uses Implements			
Notes	Extended:	Uses V Implements			
Project Info	Include Paths:	UoP2 UoP2CS1			
Click the report icon to the right	for detailed results				Ē

Figure 66. Include Paths and Files

10. Scroll down and select any of the FACE Interfaces the UoC implements. If the Life Cycle Management (LCM) Stateful interface is implemented, enter the datamodel name and datatype name of the reported and request datatype.



Figure 67. Life Cycle Management

11. Scroll down and select the FACE Interfaces that are used by the UoC. The UoC must provide an Injectable interface for each FACE Interface it uses. By specifying the candidate UoC "uses" a given interface, it indicates that it implements an Injectable Interface for that interface, and this will be tested by the CTS.

	CPP_TSS_Safetybase_TS_cpp03.pcfg - Project Configuration		_ ¤ ×
File Run Help		÷	
Project Configuration	Builder		
2			
	TSS		
General	FACE Interfaces Used:		
	LCM Initializable		
Data Model	LCM Configurable		
	LCM Connectable		
Gold Standard Libraries	Configuration Services		
	TSS Component State Persistance		
Ohiasta/Librarias	Analog I/O Interface		
Objects/Libraries	ARINC429 I/O Interface		
	ARINC825 I/O Interface		
Notes	Discrete I/O Interface		
	Generic I/O Interface		
Project Info	I2C I/O Interface		
	MIL-STD-1553 I/O Interface		
	Precision Synchro I/O Interface		
	Synchro I/O Interface		
	Serial I/O Interface		
	Health and Fault Monitoring (HMFM) Interface		
Click the report icon to the rig	ht for detailed results		

Figure 68. FACE Interfaces Used

- 12. Scroll down and enter the information regarding any FACE Life Cycle Management Stateful interfaces that are used by the UoC. If none are used, leave this section blank. Multiple Life Cycle Management Stateful interfaces may be used by a UoC. The required information for each Stateful interface are:
 - i. the data model and datatype name of the reported datatype
 - ii. the data model and datatype name of the request datatype

-	CPP_TSS_Safetybase_TS_cpp03.pcfg - Project Configuration	-	- 0	×
File Run Help	÷	-		
Project Configuration Bu	uilder			
				*
General	TSS LCM Stateful Interfaces Used by UoC			
Data Model	 Uses LCM Stateful Interfaces Reported: PV1 (Data Model: UoPModelName) Request: T2 (Data Mo 			
Gold Standard Libraries				
Objects/Libraries				
Notes				
Project Info	Remove Stateful Interface Used			
	Add New LCM Stateful Interface Used by UoC			
	Reported Type Name:			
	Reported Type UoP Model Name:			
	Request Type Name:			
Click the report icon to the right f	or detailed results			

Figure 69. Life Cycle Management Interfaces Used

Note: For TSS UoCs implementing either the TPM or CSP capabilities that need to access device drivers, please ensure that the device driver code is included/added to the compiler specific code section within the toolchain configuration as calling driver code from TSS TPM or CSPs will need to be inspected.

Generating the Gold Standard Libraries

In order to build the user's source code, the user will need FACE interface headers for any interfaces the UoC uses. For example, for a PCS the user will need any TSS headers the UoC code uses, as standardized in the FACE Technical Standard. The CTS will generate these headers for the user. Click the Generate GSLs Button in the upper left corner of the window as shown below to generate the FACE headers as well as the GSL.



Figure 70. The GSL generation button.

If providing objects for the user's UoC, the user may now build their objects using the FACE headers

generated into the GSL directory's 'include/FACE' subdirectory. Examine the contents of this directory to see the standardized header names of all non-OSS FACE Interfaces. Note that for C/C++ all FACE headers should be included with the relative path starting from the FACE directory, for example: "FACE/IOSS/Analog.hpp" The include directories to be used are described in a generated README file in the GSL directory. OSS include directories are listed and are in specific subfolders of the CTS folder goldStandardLibraries. When the user builds their object code for a UoC, the user will need to include these subfolders and include any FACE headers as "FACE/[name of header file]". (Note that the headers in this subdirectory are deleted each time the test is run, so do not store any project files in this directory.)

The GSL libraries will be generated into the GSL Directory. The user may wish to use the GSLs during development to check that their code builds against them, but there is no need to include them in their CTS project. The CTS will rebuild the appropriate GSLs when the user runs the conformance test and links them as part of the test.

In the "Provide Segment Objects/Libraries" section of the Objects/Libraries tab, the user must enter the full pathnames of the project's object and/or library files. The user may add each object file. The user may also choose the directory where object files are located. All object files in the directory specified as well as object files in subdirectories will be chosen. A combination of directories and object/library files may be specified.

	CPP_TSS_Safetybase_TS_cpp03.pcfg - Project Configuration	-		×
File Run Help	~		6	2
Project Configuration E	uilder			
				*
Conorol	TSS			
General	Provide Segment Objects/Libraries			
Data Model	Objs/Libs: C build/Base_FACE_TSS_Base_impl.o			
	build/Serialization_FACE_TSS_Message_Serialization_impl.o			
Gold Standard Libraries	build/Serialization_FACE_TSS_Serialization_impl.o			
	build/TypedTS_FACE_TSS_UoPModelName_T1_TypedTS_impl.o			
Objects/Libraries				
Notes	Generate Objects/Libraries from source code			
	Source Files:			
Project Info				
	2			
	×			
	Target Directory:			
Click the report icon to the right	for detailed results			自

Figure 71. The Project Configuration Builder, with the Objects/Libraries tab selected.

Factory Functions

FACE Interfaces, including Injectable Interfaces, are empty declarations. In order to properly test the user's code against the FACE CTS, the user must provide a file that contains a concrete implementation for each interface needed for the UoC provided. This is called a "Factory Function."

Once the user creates their Factory Function declaration and the user runs the conformance test, a test file declares a pointer to a FACE interface. Then, the CTS instantiates it by calling the Factory Function implementation that the user provided. Once instantiation is complete, it calls each method defined in the interface to ensure complete adherence to the interface.

Generation

To determine which factory functions are necessary, the user must generate the GSL for their project. After generation, the user must find a generated header/spec file named, "CTS_Factory_Functions" in the generated subfolder 'build/GSL/include', which will contain required interfaces.

Providing a Factory Function Implementation

The user must take note of the "CTS_Factory_Functions" file that was generated by the GSLs. The user must provide a file that implements each of these functions. The following paragraphs detail what the user must do per each language the user's UoC implements.

For C/C++, this file (CTS_Factory_Functions .h or .hpp) will contain the declarations of all expected factory functions that the CTS requires for testing the user's UoC. The implementation for each function must instantiate the corresponding concrete class and return a pointer to that object (the return type will be a pointer to the FACE 'abstract' class). Returning a null pointer is not acceptable. This source file must be provided with the user's project and will be reviewed to ensure it instantiates the user's UoC's concrete class for that interface.

For Ada, this will generate a spec file (.ads) cts_factory_functions.ads which has the procedures the user must implement in the source file. The source file for Ada must be named "cts_factory_functions.adb" and implement each of these procedures, returning a concrete version of each type as an access type. In the text field labeled "Source file with factory functions for interfaces provided (C/C++/Ada only)", use the '...' button to the right to browse for the source file. **Any header files included by the source file must exist in one of the Include Paths specified above.**

For Java, a source file named CTS_Factory_Functions.java will be generated in the factory/ subfolder (package subfolder). The user must fill in the implementation of each function, add any imports, and add this to the user's project in the CTS in this file field. Note that this file will NOT be overwritten so if the interfaces the UoC uses have changed, the user must delete their file in order to regenerate a new one with the new set of functions to implement.

Validating and Testing a Project

- 1. Select **1** to verify that the Project Configuration File is valid.
- 2. Click the **()** button at the top of the screen to test the segment. (This may take a few minutes). The results will be written to a PDF file. The directory of the results file will be in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.

Special Verification Cases

TSTA Adapter UoC Using and Providing TS Base

CR 564 allows a TSTA Adapter UoC to use the TS Base interface via the injectable interface. In addition, CR 585 allows a TSTA Adapter UoC to provide the TS Base interface to PCS and PSSS UoCs. Therefore, a TSTA Adapter UoC is allowed to use as well as provide the TS Base interface. Two conformance tests need to be performed to verify such a TSS UoC, one test to verify the using aspect of the TS Base interface and a second test to verify the providing aspect of the TS Base interface. Each conformance test shall use separate project file (pcfg) with the respective tss_base and uses_tss_base options set to true as well as separate CTS_Factory implementations with definition for retrieving either the implementation of the TS Base injectable or the TS Base.

7.5. Testing an I/O Services Segment (IOS) UoC

The following subsections details instructions to successfully generate a valid project configuration file for an IOS UoC and how to run a test using the Conformance Test Suite. More information about each projection configuration option can be found in the subsections of Project Configuration Files.

7.5.1. What the User Must Provide

The user must provide the following inputs to the CTS:

- The project's object files (C/C++/Ada) or class/jar files (Java). Alternatively, source files can be provided, and the CTS will build them into object or class files using the toolchain configuration.
- The project's header files (C/C++) or spec files (Ada).
- The project's USM.
- The project's toolchain file.

7.5.2. Test Procedures

Providing Project Context

- 1. Successfully install the CTS.
- 2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.

File Run Help	۵
Futue Airborne Copubility Environment* Welco	me to FACE Conformance Test Suite FACE Technical Standard Edition 3.0
Recent Projects	Quick Start
	Run Conformance Test
	Create a Project Configuration
	Create a Toolchain Configuration
No Recent Projects	🛞 Preferences
	Cocumentation

Figure 72. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	Project - FACE Conformance Test Suite 3.0r0-SNAPS	нот 📀
Create a New Pro	oject Configuration	
Project Name:	UntitledProject	p
Project Location:	/home/tstittleburg/CTSProjects	
	Ok Ci	ancel

Figure 73. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.

C_IOSS_General_Analog.pcfg - Project Configuration _ D							
File Run Help		~					
Project Configuration Builder							
		۲	*				
General	ral						
Bas Data Model Seg Lan	e Directory: ment: guage:	/home/cts/Desktop/dev/CTS3x/sample/projects/C/IOSS/Gener IOSS C99	···· •				
Gold Standard Libraries Ope	file: erating Environment:	General POSIX	* *				
Objects/Libraries POS	SIX Multi Process:	Use Multi Process APIs	_				
Notes Ope	enGL:	None	•				
Project Info UoC	lchain: C Name:	///.toolchains/C99/General/C99_NonOSS_Genera	+				
Click the report icon to the right for deta	iled results		向				

Figure 74. Project Configuration Builder General tab

- 6. Fill in all options on the General tab for
 - a. Base Directory
 - b. Select "IOS" as segment
 - c. The Language the candidate UoC was written in
 - d. The OSS profile the candidate UoC was intended
 - e. The intended operating environment of the UoC
 - i. Enable POSIX multi process APIs if required
 - ii. If ARINC653 or POSIX ARINC653 was selected as the operating environment, select what ARINC653 version is required
 - f. Add the targeted toolchain path
 - g. Set the UoC name
- 7. Select the Data Model tab to display the data model information below.
 - a. Set the path to the SDM and USM. This directory is relative to the base directory set in the General tab.

C_IOSS_General_Analog.pcfg - Project Configuration _ 📮 🗖							
File Run Help	(
Project Configuration B	uilder						
		*					
	Data Model						
General	Shared Data Model:						
Data Model	UoP Supplied Model:						
Gold Standard Libraries	Entity Uniqueness Observable Uniqueness						
Objects/Libraries	UoP: Choose a UoP	v					
Notes	Associated Connections:						
Project Info							
Click the report icon to the right f	for detailed results						

Figure 75. Data Model tab

- 8. Select the Gold Standard Libraries tab to display the options below.
 - a. Set the directory where the gold standard libraries will be generated and stored for the test.
 - **NOTE** This directory is relative to the base directory set in the General tab.

	C_IOSS_General_Analog.pcfg - Project Configuration	- 0	×
File Run Help	÷		2
Project Configuration B	uilder		
2 🗟 🔏 💾			*
	Gold Standard Libraries		
General	GSL Directory: /home/cts/Desktop/dev/CTS3x/sample/projects/C/IOSS/General/Anal	iog/b	
Data Model			
Gold Standard Libraries			
Objects/Libraries			
Notes			
Project Info			
Click the report icon to the right f	for detailed results		

Figure 76. Gold Standard Libraries tab

- 9. Select the Objects/Libraries tab to display the IOS components options shown below. For C/C++ projects, use the list boxes to add the include files and include paths (if applicable) for the concrete interface implementations provided by the UoC. All 'include files' must exist in one of the 'include paths'. Any files included by the concrete implementation of Factory Functions must exist in one of the Include Paths specified. More details about Factory Functions are found in Section 7.5.2.3. More information about all options in the Object/Libraries tab are detailed in Project Configuration Obj/Lib tab.
 - a. If the user is providing object files for their UoC, before providing the user's object or library files, they must build them against the Gold Standard Library headers. The CTS will generate the FACE headers for any interface the UoC uses so that the user can build their source code against those. Skip selecting the UoC's object files until the user has generated the GSLs and FACE headers and has built their UoC code against these headers. Therefore, skip the section on selecting object files for now.

C_IOSS_General_Analog.pcfg - Project Configuration _							
File Run Help	(
Project Configuration B	Builder						
		*					
Conoral	1055						
General	Interfaces Defined: 🗸 Analog I/O Interface						
Data Madal	ARINC429 I/O Interface						
Data Model	ARINC825 I/O Interface						
Gold Standard Libraries	Discrete I/O Interface						
	Generic I/O Interface						
	I2C I/O Interface						
Objects/Libraries	MIL-STD-1553 I/O Interface						
	Precision Synchro I/O Interface						
Notes	Synchro I/O Interface						
	Serial I/O Interface						
Project Info	t						
	V						
	+						
Click the report icon to the right	for detailed results	2					

Figure 77. Include Paths and Files

10. Scroll down and select any of the FACE Interfaces the UoC implements. If the Life Cycle Management (LCM) Stateful interface is implemented, enter the datamodel name and datatype name of the reported and request datatype.



Figure 78. Life Cycle Management

11. Scroll down and select the FACE Interfaces that are used by the UoC. The UoC must provide an Injectable interface for each FACE Interface it uses. By specifying the candidate UoC "uses" a given interface, it indicates that it implements an Injectable Interface for that interface, and this will be tested by the CTS.



Figure 79. FACE Interfaces Used

- 12. Scroll down and enter the information regarding any FACE Life Cycle Management Stateful interfaces that are used by the UoC. If none are used, leave this section blank. Multiple Life Cycle Management Stateful interfaces may be used by a UoC. The required information for each Stateful interface are:
 - i. the data model and datatype name of the reported datatype
 - ii. the data model and datatype name of the request datatype

	C_IOSS_General_Analog.pcfg - Project Configuration		_ • ×
File Run Help		÷	
Project Configuration B	uilder		
			*
	IOSS		
General	LCM Stateful Interfaces Used by UoC		
Data Model	Uses LCM Staterul Interfaces		
Gold Standard Libraries			
Objects/Libraries			
Neter			
Notes	Remove Stateful Interface Lised		
Project Info	Keniove Statelar interface Osca		
	Add New LCM Stateful Interface Used by UoC		
	Reported Type Name:		
	Reported Type UoP Model Name:		
	Request Type Name:		I
Click the report icon to the right	for detailed results		

Figure 80. Life Cycle Management Interfaces Used

Generating the Gold Standard Libraries

In order to build the user's source code, the user will need FACE interface headers for any interfaces the UoC uses. For example, for a PCS the user will need any TSS headers the UoC code uses, as standardized in the FACE Technical Standard. The CTS will generate these headers for the user. Click the Generate GSLs Button in the upper left corner of the window as shown below to generate the FACE headers as well as the GSL.



Figure 81. The GSL generation button.

If providing objects for the user's UoC, the user may now build their objects using the FACE headers generated into the GSL directory's 'include/FACE' subdirectory. Examine the contents of this directory to see the standardized header names of all non-OSS FACE Interfaces. Note that for C/C++ all FACE headers should be included with the relative path starting from the FACE directory, for example: "FACE/IOSS/Analog.hpp" The include directories to be used are described in a generated

README file in the GSL directory. OSS include directories are listed and are in specific subfolders of the CTS folder goldStandardLibraries. When the user builds their object code for a UoC, the user will need to include these subfolders and include any FACE headers as "FACE/[name of header file]". (Note that the headers in this subdirectory are deleted each time the test is run, so do not store any project files in this directory.)

The GSL libraries will be generated into the GSL Directory. The user may wish to use the GSLs during development to check that their code builds against them, but there is no need to include them in their CTS project. The CTS will rebuild the appropriate GSLs when the user runs the conformance test and links them as part of the test.

In the "Provide Segment Objects/Libraries" section of the Objects/Libraries tab, the user must enter the full pathnames of the project's object and/or library files. The user may add each object file. The user may also choose the directory where object files are located. All object files in the directory specified as well as object files in subdirectories will be chosen. A combination of directories and object/library files may be specified.



Figure 82. The Project Configuration Builder, with the Objects/Libraries tab selected.

Factory Functions

FACE Interfaces, including Injectable Interfaces, are empty declarations. In order to properly test the user's code against the FACE CTS, the user must provide a file that contains a concrete implementation for each interface needed for the UoC provided. This is called a "Factory Function."

Once the user creates their Factory Function declaration and the user runs the conformance test, a test file declares a pointer to a FACE interface. Then, the CTS instantiates it by calling the Factory Function implementation that the user provided. Once instantiation is complete, it calls each method defined in the interface to ensure complete adherence to the interface.

Generation

To determine which factory functions are necessary, the user must generate the GSL for their project. After generation, the user must find a generated header/spec file named, "CTS_Factory_Functions" in the generated subfolder 'build/GSL/include', which will contain required interfaces.

Providing a Factory Function Implementation

The user must take note of the "CTS_Factory_Functions" file that was generated by the GSLs. The user must provide a file that implements each of these functions. The following paragraphs detail what the user must do per each language the user's UoC implements.

For C/C++, this file (CTS_Factory_Functions .h or .hpp) will contain the declarations of all expected factory functions that the CTS requires for testing the user's UoC. The implementation for each function must instantiate the corresponding concrete class and return a pointer to that object (the return type will be a pointer to the FACE 'abstract' class). Returning a null pointer is not acceptable. This source file must be provided with the user's project and will be reviewed to ensure it instantiates the user's UoC's concrete class for that interface.

For Ada, this will generate a spec file (.ads) cts_factory_functions.ads which has the procedures the user must implement in the source file. The source file for Ada must be named "cts_factory_functions.adb" and implement each of these procedures, returning a concrete version of each type as an access type. In the text field labeled "Source file with factory functions for interfaces provided (C/C++/Ada only)", use the '...' button to the right to browse for the source file. **Any header files included by the source file must exist in one of the Include Paths specified above.**

For Java, a source file named CTS_Factory_Functions.java will be generated in the factory/ subfolder (package subfolder). The user must fill in the implementation of each function, add any imports, and add this to the user's project in the CTS in this file field. Note that this file will NOT be overwritten so if the interfaces the UoC uses have changed, the user must delete their file in order to regenerate a new one with the new set of functions to implement.

Validating and Testing a Project

- 1. Select 📴 to verify that the Project Configuration File is valid.
- 2. Click the **()** button at the top of the screen to test the segment. (This may take a few minutes). The results will be written to a PDF file. The directory of the results file will be in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.

7.6. Testing an Operating System Segment (OSS) UoC

The following subsections details instructions to successfully generate a valid project configuration file for an OSS UoC and how to run a test using the Conformance Test Suite. More information about each projection configuration option can be found in Project Configuration Files.

7.6.1. What the User Must Provide

The user must provide the following inputs to the CTS:

- The OS's include path.
- The target OS object files.

7.6.2. Test Procedures

Providing Project Context

- 1. Successfully install the CTS.
- 2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.



Figure 83. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	roject - FACE Conformance Test Suite 3.0r0-SNA	PSHOT
Create a New Pro	oject Configuration	
		_
Project Name:	UntitledProject	.p
Project Location:	/home/tstittleburg/CTSProjects	
	Ok	Cancel
	ŬK.	Cancel

Figure 84. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.

	C_OSS_ARINC653.	pcfg - Project Configuration _ r	x נ
File Run Help		÷	
Project Configuration B	Builder		
			*
	General		
General Data Model	Base Directory: Segment:	/home/cts/Desktop/dev/CTS3x/sample/projects/C/OSS/Genera OSS	····
Gold Standard Libraries	Profile: Operating Environment:	General ARINC653	• •
Objects/Libraries	POSIX Multi Process:	Use Multi Process APIs	•
Notes	OpenGL:	OpenGL SC API & OpenGL SC 2.0 API & OpenGL ES 2.0 API	
Project Info	Toolchain: UoC Name:	///toolchains/C99/General/C99_OSS_General_tox Type UoC Name	+
Click the report icon to the right	for detailed results		向

Figure 85. Project Configuration General tab

- 6. Fill in all options on the General tab.
- 7. Select the Gold Standard Libraries tab to display the options below.

	C_OSS_ARINC653.pcfg - Project Configuration	-	• ×
File Run Help	÷		
Project Configuration B	uilder		
			*
	Gold Standard Libraries		
General	GSL Directory: /home/cts/Deskton/dev/CTS3x/sample/projects/C/OSS/General/ARI	NC653	
Data Model		10055	
Gold Standard Libraries			
Objects/Libraries			
Notes			
Project Info			
Click the report icon to the right	for detailed results		

Figure 86. The Project Configuration Builder with the Gold Standard Libraries tab selected.

- 8. Set the directory where the GSL will be generated and stored for the test. This directory is relative to the base directory set in the General tab.
- 9. Select the Objects/Libraries tab.
 - a. The user must check each OS API they wish to test. Notice their options are now editable.
 - b. For each OS API under test, place any specific compiler flags that are needed. General compiler flags can be specified under the Build tab. These flags should be unique to the OS API under test.
 - c. For each OS API under test, place any specific linker flags that are needed. General linker flags can be specified under the Build tab. These flags should be unique to the OS API under test.
 - d. For each OS API under test, enter any directories that should be in the include path for each OS API interface.
 - e. For each OS API under test, enter the full pathnames to any header files associated with the interface. These files must be in one of the directories specified under 'compiler paths' (include paths). Any files included by the Factory Functions (see next few steps) must exist in one of the Include Paths specified.

	C_(OSS_ARINC65	3.pcfg - Proje	ct Configuration			- 1	• ×
File Run Help						÷		
Project Configuration Buil	der							
								*
General	DSS]
Data Model	ARINC 653 C99	9 Std Library	POSIX HM	M Configuration	LCM Khronos I	EGL 1.4 Ope	nGL SC	Ope
Gold Standard Libraries	Compiler Flags: Linker Flags:							
Objects/Libraries	Objs/Libs:	(]//bui	ld_GSL/arinc6	3GeneralGoldLib.a				
Notes		*						
Project Info	Compiler Paths:	+	//goldStanda	rdLibraries/C/src/OS	5/ARINC-653/gener	al		
		÷						
	Linker Paths:	+ *						
		+///	//goldStanda	rdLibraries/C/src/OS	5/ARINC-653/gener	al/ARINC653.h		
	Include Files:	÷						
_	Source file with fact	ory functions	for interfaces	provided (C/C++/Ad	a only):	-		
Click the report icon to the right for	detailed results							

Figure 87. The Project Configuration Builder with the Objects/Libraries tab selected.

Table 14	OSS Tests	hased	on	language	and	nrofile
<i>Iubic</i> 14.	000 16363	Duseu	υn	unguuge	unu	projue.

Languag e/ Profile	ARINC 653	C Std Lib	C++ Std Lib	HMFM	Java	Khronos Group EGL 1.4	OpenGL ES 2.0	OpenGL SC 2.0	POSIX	Config uration	LCM
C/GP	Х	Х		Х		Х	Х		Х	Х	Х
C/SB, C/SE	Х	Х		Х				Х	Х	Х	Х
C/S	Х	Х		Х					Х	Х	Х
C++/All			Х	Х						Х	Х
Ada/All	Х			Х						Х	Х
Java/GP					Х					Х	Х

"Language/Profile" column acronyms in Table 14 are defined as:

- GP: General Purpose
- SB: Safety Base
- SE: Safety Extended
- S: Security
- All: All profiles

Generating Gold Standard Libraries

In order to build the user's source code, the user will need FACE interface headers for any interfaces the UoC uses. For example, for a PCS the user will need any TSS headers the UoC code uses, as standardized in the FACE Technical Standard. The CTS will generate these headers for the user. Click the Generate GSLs Button in the upper left corner of the window as shown below to generate the FACE headers as well as the GSL.



Figure 88. The GSL generation button.

If providing objects for the user's UoC, the user may now build their objects using the FACE headers generated into the GSL directory's 'include/FACE' subdirectory. Examine the contents of this directory to see the standardized header names of all non-OSS FACE Interfaces. Note that for C/C++ all FACE headers should be included with the relative path starting from the FACE directory, for example: "FACE/IOSS/Analog.hpp" The include directories to be used are described in a generated README file in the GSL directory. OSS include directories are listed and are in specific subfolders of the CTS folder goldStandardLibraries. When the user builds their object code for a UoC, the user will need to include these subfolders and include any FACE headers as "FACE/[name of header file]". Note that the headers in this subdirectory are deleted each time the test is run, so do not store any project files in this directory.

The GSL libraries will be generated into the GSL Directory. The user may wish to use the GSLs during development to check that their code builds against them, but there is no need to include them in their CTS project. The CTS will rebuild the appropriate GSLs when the user runs the conformance test and links them as part of the test.

In the "Provide Segment Objects/Libraries" section of the Objects/Libraries tab, the user must enter the full pathnames of the project's object and/or library files. The user may add each object file. The user may also choose the directory where object files are located. All object files in the directory specified as well as object files in subdirectories will be chosen. A combination of directories and object/library files may be specified.

Factory Functions

FACE Interfaces, including Injectable Interfaces, are empty declarations. In order to properly test the user's code for FACE Conformance, the user must provide a file that contains a concrete implementation for each interface needed for the UoC provided. This is called a "Factory Function."

Once the user creates their Factory Function declaration and the user runs conformance test within

the CTS, a test file declares a pointer to a FACE interface. Then, the CTS instantiates it by calling the Factory Function implementation that the user provided. Once that is complete, it calls the methods defined in the interface to ensure complete adherence to the interface.

Generation

To determine which factory functions are necessary, the user must generate the GSL for their project. After generation, the user must find a generated header/spec file named, "CTS_Factory_Functions" in the generated subfolder 'build/GSL/include', which will contain required interfaces.

Providing a Factory Function Implementation

The user must take note of the "CTS_Factory_Functions" file that was generated by the GSLs. The user must provide a file that implements each of these functions. The following paragraphs detail what the user must do per each language the user's UoC implements.

For C/C++, this file will contain the declarations of all expected factory functions that the CTS requires for testing the user's UoC. The user must provide a source file that implements each of these functions. The implementation for each function must instantiate the corresponding concrete class and return a pointer to that object (the return type will be a pointer to the FACE base class). Returning a null pointer is not acceptable. This source file must be provided with the user's project and will be reviewed to ensure it instantiates the UoC's concrete class for that interface.

For Ada, this will generate a spec file (.ads) cts_factory_functions.ads which has the procedures the user must implement in the source file. The source file for Ada must be named "cts_factory_functions.adb" and implement each of these procedures, returning a concrete version of each type as an access type. In the text field labeled "Source file with factory functions for interfaces provided (C/C/Ada only)", use the '...' button to the right to browse for the source file. *Any header files included by the source file must exist in one of the Include Paths specified above.* An example for a C project is shown below.

For Java, a source file named CTS_Factory_Functions.java will be generated in the factory/ subfolder (package subfolder). The user must fill in the implementation of each function, add any imports, and add this to the user's project in the CTS in this file field. Note that this file will NOT be overwritten so if the interfaces the UoC uses have changed, the user must delete their file in order to regenerate a new one with the new set of functions to implement.

ile Run Help		←
roject Configuration Bu	uilder	
2 8 18 1		*
General	oss	
Data Model	C++ Std Library HMFM Configuration LCM	
Gold Standard Libraries	Vote: Ensure the toolchain selected is intended for an OSS Configuration Services UoC Compiler Flags:	
Objects/Libraries	Linker Flags:	
Notes	build/initializable_FACE_LCM_initializable_InitializableInstance_impl.o	
Project Info	0	
	Compiler Paths: +	
	\$	
	Linker Paths:	
	×	
	×	
	Include Files:	

Figure 89. The Project Configuration Builder with the Objects/Library tab selected, within the Configuration subtab.

Validating and Testing a Project

- 1. Select 📴 to verify that the Project Configuration File is valid.
- 2. Click the **b**utton at the top of the screen to test the segment. (This may take a few minutes). The results will be written to a PDF file. The directory of the results file will be in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.
- 3. The result will be pass or fail if the OS supplies the necessary calls based on the profile.

7.7. Testing a Data Model

The following sections detail how to test a USM with the conformance test suite.

7.7.1. What the User Must Provide

The user must provide the following inputs to the CTS:

• The UoC data model file.

7.7.2. Test Procedures

1. Successfully install the CTS.

2. Start the conformance test suite by running the run_CTS_GUI.py script in the main test suite directory from the command line.



Figure 90. Conformance Test Suite main menu

3. Import or create a new Project Configuration file by clicking "Create a Project Configuration".

Create New P	roject - FACE Conformance Test Suite 3.0r0-SNAPSHOT	×
Create a New Pro	oject Configuration	
Project Name:	UntitledProject .p.	
Project Location:	/home/tstittleburg/CTSProjects	
	Ok Cance	1

Figure 91. Create New Project Configuration

- 4. Fill in Project Name and Project Location then press Ok to launch the project configuration builder.
- 5. Navigate to the project configuration builder.
- 6. Assure that the PCS/PSS/TSS is selected in the Segment dropdown of the General tab of the Project Configuration Builder.

	*CPP_PCS_Safetyext_cpp(03.pcfg - Project Configuration _ G	ı x
File Run Help		÷	
Project Configuration B	uilder		
			*
General	General		
Data Model	 Base Directory: Segment: Language: Profile: Operating Environment: POSIX Multi Process: ABINC653 Part 1 Version: 	/home/cts/Desktop/dev/CTS3x/sample/projects/CPP/PCS PCS C++03	···· •
Gold Standard Libraries		Safety Extended POSIX ARINC653	* *
Objects/Libraries		ess: Version: 2010	
Notes	OpenGL:	None	•
Project Info	Toolchain: UoC Name:		+
Click the report icon to the right	for detailed results		

Figure 92. Select PCS in the General Tab of the Project Configuration Builder

7. Select the Data Model tab to display the options below.



ck the report icon to the right for detailed results...

Figure 93. Projection Configuration Builder Data Model tab

- 8. Select the shared data model (SDM) file associated with the segment under test.
- 9. Optionally select the conditional Object Constraint Language (OCL) constraints governing USM and DSDM content.
 - Select the Entity Uniqueness checkbox to define that the Entity is unique in a Conceptual Data Model.
 - An Entity is unique if the set of its Characteristics is different from otherNOTEEntities' in terms of type, lowerBound, upperBound, and path (for
Participants).
 - Select the Observable Uniqueness checkbox to define that the Entity does not compose the same Observable more than once.
- 10. Select the UoP Supplied Model file associated with the segment under test. The test suite will analyze the USM file, determining its validity and the Units of Portability found in the data model file.
- 11. You may see data types associated with a UoP by clicking on the properties button.
- 12. Select the Units of Portability to use with the segment under test.
- 13. Click the Test Data Model button.
 - ton. 🏼 🏶
- 14. The results will be written to a PDF file. The directory of the PDF results will be located in the directory of the project configuration file. This directory path will be listed in the "Output File Location" of the Conformance Test Results page.

7.8. Considerations for Testing an Ada Segment

Testing an Ada segment requires a small variation in the testing procedures from C and C++. According to the standard, Ada Runtime Libraries are allowed, but if the Runtime Library is packaged with the UoC, it must only use standard POSIX calls allowed according to the profile and operating environment. If the Ada Runtime Libraries are part of the logical OSS, the use of the Ada Runtime Libraries is verified via Inspection. In order to perform the link test for a packaged Ada Runtime Library, you must include the Ada Runtime Library as part of your object/library files. Additionally, you must compile the correct Gold Standard POSIX library to include as part of your object library files. Since the test suite only supports compilation for one language at a time, you must build the POSIX libraries before proceeding with Ada testing. This can be done by changing your configuration from Ada to C, with the correct C compiler options, and generate the gold standard libraries as described below. Once the libraries have been built, change the configuration back to Ada, add the POSIX and Runtime libraries to your segment configuration and proceed with the test. The test suite does generate Ada gold standard HMFM and ARINC 653 libraries.

7.9. Considerations for Testing a Java Segment

Testing a Java segment is very different from testing procedures from other languages. Since Java is inspected directly instead of using a link test, there is not an option to generate gold libraries in Java. For each test, Java Class Paths are used instead of object/library files. Include paths are not used under Java tests. Under most systems, *javac* should be used as the compiler and *jar* should be

used as the archiver. The object file extension should be set to *class* in the project's toolchain file.

7.10. Viewing Test Suite Results

Once the run Conformance test button is pressed, the test suite will conduct the conformance test be stored in PDF format. and the results will The file will be named FACEConformanceTest_Name_of_PCFG.pdf in the same directory as the pcfg file tested. All log files generated in the test will also be found in the log directory, although the same log files are found inside the PDF report. An example of a passable OSS component is given in the figure below:



Figure 94. A successful conformance test message.

The output of the CTS is written to a PDF report. The path of the PDF report will be displayed in the Output File Location section.



Figure 95. An example conformance test report.

The PDF report will detail toolchain and project configuration information along with source code and/or log results associated with a test. Examples of the conformance test results can be seen below.

🖹 🛽 🛽 🖪 🖉 🔍 🔍	(anonymous) FACEConformanceTest_arinc653_OSS_LANG_C.pdf	 x
Index 🗸 🗶	ARINC 653 Conformance Test → PASSED	^
Distribution 2	$TIME \rightarrow PASSED$	
Table of Cont 3	Tables THED WAIT conformance . DACCED	
▼ Configuration 5	Testing TimeD_wAIT conformance → PASSED	0
Project Con 5	conformanceInterfaceTestsC/OSS/ARINC653/general/TIME/APEX_TIME.TIMED_WAIT-test.c	
Toolchain C 6	/* */ #include "ARINC653_CONFORMANCE_TEST.h"	
Conformance 8	<pre>/* Used to catch assertions at compile time */ #define FACE_STATIC_ASSERT(e) char face_static_assert(e ? 1 : -1)</pre>	
▼ OS Segment 8	int main(int args, char "args()) (/* Function Rignature Conformance Test */	
	<pre>void (*TINED_MAIT_TEST_DTN) (/* in */ SYSTEM_TIME_TYPE DELAY_TIME,</pre>	
TIME → P 8	/* out */ RETURN_CODE_TYPE * RETURN_CODE = TINED_NAIT;	
Testing 8	Testion	
Testing 8	ewd: /home/nsmith/conformancetestsuite/conformancetnterfaceTests/C/038/ARTHC-65	
Testing 9	3/general/TIME command: cc -I/home/msmith/conformancetestsuite/toolchain/generated_files/examp la.C.005 teolchain	
Testing 9	-I/home/mamith/conformancetestauite/conformanceInterfaceTests/C/OSE/ARINC-653 - I/home/mamith/conformancetestsuite/coldEtandardLibraries/C/arc/OSE/ARINC-653/ce	
 PROCESS 11 	ners1 - I/home/msmith/conformancetestsuite/conformanceInterfaceTests/C/OSS/ARIH:-653	
Testing 11	-o APEX_TIME.TIMED_WAIT-test.o -std*c99 -c APEX_TIME.TIMED_WAIT-test.c return code: 0	
Testing 11	Test Log:	
Testing 12	cvd: /home/momith/conformancetestsuite/conformanceInterfaceTests/C/028/AAINC-65	
Testing 12	command: 1d APEX_TIME.TIME.THED_NAIT-test.o /home/mamith/conformancetestauite/tests /upps/C/build/OSL/arine/SSIGeneral/Coldbib.a =la =o APEX_TIME_TIMED_MAIT-test	
Testing 13	return code: 0 output:	
Testing 13	1d: warming: cannot find entry symbol _start; defaulting to 0000000004001f3	
Testing 14	Testing PERIODIC_WAIT conformance → PASSED	
Testing 14	Test Code: conformanceInterfaceTesta/C/OSS/ARINC-653/general/TIME/APEX_TIME.PERIOD IC_WAIT-tost.c	
Testing 15	<pre>/* */ #include "ARINC553_CONFORMANCE_TEST.h"</pre>	
Testing 15	<pre>/* Used to catch assertions at compile time */ #define FACE_STATIC_ASSERT(e) char face_static_assert[e ? 1 : -1]</pre>	
Testing	int main(int arge, char "argv()) ((7. Function Simulum Confermance Text X/	
Testing 17	void ("PERICOIC_WAIT_TEST_FIN") /* out */ RETURN CODE_TYPE * RETURN.CODE	
Testing 17	= FERIODIC_NAIT;	
Testing 18	Test Log:	
- PARTITIO 10 *	end: /hone/nsmith/conformancetestsuite/conformanceInterfaceTests/C/088/ARINC-65 3/general/tIME	~

Figure 96. A conformance test report scrolled to show report contents.

The source of the non-conformance for a failed conformance test can be determined by examining
the test source code and resulting log files.

Appendix A: References

- 1. The Open Group, "FACE[®] Technical Standard, Edition 3.0," November 2017. [Online]. Available: https://publications.opengroup.org/.
- 2. The Object Management Group, "Interface Definition Language," March 2018. [Online]. Available: https://www.omg.org/spec/IDL/About-IDL/.

Appendix B: Using the CTS Via Command Line Interface (CLI):

There are a number of options you can use when running the test suite start-up python script (conformance_test.py).

If the test suite is launched with a configuration file listed, the test suite will run without the GUI and save the results to the log directory listed in the configuration. The test suite will exit with a return code of 0 if the segment(s) under test passes verification and a non-zero value otherwise as defined in Table 16. These can be useful for automated testing of segments without user interaction.

Multiple configuration files can be passed to run by test suite, but it is important to have different log directories in each configuration file, otherwise the test results would be overwritten by subsequent tests. When running multiple configuration files, the log files will be overwritten with each subsequent run. Additionally, the script will exit on the first non-zero exit code from the series of configuration files.

The user must be in the root directory of their CTS installation. Then, point to the face_conformance_app file:

```
cd face_conformance_app
python conformance_test.py [options] [config_file1] [config_file2] ...
```

The usage options from the start-up script is shown below.

Switch	Definition
-h,help	Show this help message and exit.
-p PORT_VALUE,port=PORT_VALUE	Used in coordination with the CTS_GUI. Port used to communicate with GUI supplied socket server.
-t, –time_stamp	Generates a time stamp to be added to the report filename (assuring unique test run names).
-r REPORT_FILENAME,report_filename=REPORT_FILENAME	Full path to the conformance test report PDF file. Default filename is FACEConformanceTest_SEGMENT_PROJECT_NAME.pdf in the same directory as the segment project file.
-v,verify	Verifies that a project configuration is valid for running conformance tests. Return code is 0 if valid, and non-zero if invalid. Saves a log(PROJECT_CONFIG_NAME.ver_log) to the same directory as the configuration file, and sends the results to stdout.
-f,disable_pdf	Disables PDF writer.
-g,gold	Build GSLs for given project.
-d,datamodel	Test only data model. Return code is 0 if valid, and non-zero if invalid.
-a DESTINATION_DIR,allgold=DESTINATION_DIR	Build all GSLs to specified directory

Table 15. Command Line Options

Switch	Definition
-o FACE_PROFILE,profile=FACE_PROFILE	Profile of GSLs to build specified directory, only important with -a. If not given, all profiles used. Acceptable values: general, safetyExt, safetyBase, security
-i,interfaces	Create folder of interfaces only (C/C++ only as of this version - these are the header files for the project)

The error codes returned from the command line usage are defined below.

Table	16.	Command	d Line	Return	Codes
100000	T 0.	00111111111111	LILLO	1.0.000	000000

Error Code	Definition
0	The segment under test passed verification (or terminates as expected if no verification tests are run).
1	A catch-all for a fatal error or exception that occurred.
2	Invalid command line options
3	Invalid toolchain configuration (.tcfg) file
4	Invalid project configuration (.pcfg) file
5	The segment under test did not pass verification.
6	The data model was invalid.
7	A test result requires the user to examine the log file to determine success or failure.
8	A non-critical test fails, such as a file is missing that was expected but not required.
9	An issue occurred that prevented the tests from being performed.

Appendix C: Glossary

Acronym	Acronym Meaning
АРІ	Application Programming Interface
CR	Change Request
CSP	Component State Persistence
CTS	Conformance Test Suite
CVM	Conformance Verification Matrix
DSDM	Domain-Specific Data Model
FACE	Future Airborne Capability Environment
GSL	Gold Standard Library
GTRI	Georgia Tech Research Institute
GUI	Graphical User Interface
IDL	Interactive Data Language
IOSS	I/O Services Segment
ISIS	Institute for Software Integrated Systems
JDK	Java Development Kit
LCM	Life Cycle Management
NAVAIR	Naval Air Systems Command
OCL	Object Constraint Language
OSS	Operating System Segment
PCS	Portable Components Segment
PEO	Program Executive Office
PR	Problem Report
PSSS	Platform Specific Services Segment
SDM	Shared Data Model
TPM	Transport Protocol Mediation
TSS	Transport Services Segment
UDDL	Open Universal Domain Description Language
UoC	Unit of Conformance
UoP	Unit of Portability
USM	UoP Supplied Model
VA	Verification Authorities

Appendix D: Constraints

POSIX and ARINC interface testing is performed on functions only. Data types and constants are not tested comprehensively. A POSIX or ARINC conformance test should be used to fully test those aspects.

Appendix E: Known Issues

- **NOTE** Any issue found concerning the CTS should be reported to https://ticketing.facesoftware.org.
- **NOTE** The Configuration file structure has changed greatly from version 2.0 of the conformance test suite and cannot be ported into 3.0 conformance tests.

Known Issues in this CTS Release

- 1. A Failed test result sometimes generates an "Inspection Required" overall test report result.
- 2. Some windows in the CTS GUI may not be sized correctly to fit all of their contents.
- 3. CTS Java sample projects and datamodel need to be updated. Sample projects that rely on the sample project datamodel are disabled.
- 4. Extracting CTS toolsuite to a long folder path on Windows can cause problems with the sample projects due to path length limitations and command string limitations on Windows.
 - Compiling sample UoCs may fail.
 - Running conformance test on sample UoCs may be unsuccessful.
- 5. Configuring a toolchain to use compiler optimizations will result in false positives. **DO NOT USE COMPILER OPTIMIZATIONS WITH THE CTS.**
- 6. Archive command (ar) is unable to create gold standard libraries on Windows for some of the sample C and C++ projects using relative path when CTS is extracted to a long folder path. Absolute paths is currently being used since it executes as expected with absolute paths.
- 7. In the sample directory, the testUtility.py script always regenerates .tcfgtemplate files before it creates .tcfg files when the --toolchains option is used.
- 8. The IDL to Ada compiler does not generate compilable code for IDL consisting of a sequence/array of struct or union in some cases. (FACE PR/CR Ticket 1045 has been filed to address the issue in the Technical Standard.)
- 9. In the Documentation view, collapsing the root element (Welcome) can introduce bogus siblings to the root element.
- 10. OpenGL combobox on project configuration page allows selecting values for TSS and IOSS UoCs, which is not allowable by the Technical Standard.

Appendix F: Acknowledgments

The test suite utilizes the following freely distributable software packages:

Software Package	Details
stringtemplate 3.1	http://www.stringtemplate.org/
	Author: Benjamin Niemann
	License: BSD
Protocol Buffers - Google's data interchange format	http://code.google.com/p/protobuf/
	Copyright 2008 Google Inc. All rights reserved.
	License: New BSD

Appendix G: Approved Corrections to Technical Standard by CTS Version

Each release of the Conformance Test Suite incorporates a list of published Approved Corrections to the FACE Technical Standard. The list of published Approved Corrections incorporated grows with each release.

Using the CTS to test a UoC may apply some of those Approved Corrections to the test outcome. In effect, the Software Supplier adopts those Approved Corrections corresponding to their UoC when using the CTS. The Software Supplier is encouraged to use the list to identify the Approved Corrections corresponding to their UoC. The identified Approved Corrections should be listed on the Statement of Conformance submitted to the FACE VA and on the Statement of Verification from the FACE VA.

The following table lists which Technical Standard Approved Corrections were addressed in a CTS version. The table should be read as being additive. For a given CTS version, the CTS incorporates the Approved Corrections for listed for its version and all previous versions of the CTS.

NOTE

Not all Approved Corrections in the table apply to all UoCs. A Software Supplier should work with the Verification Authority to determine the appropriate subset of Approved Corrections.

CTS Version	CR#	Consortium Title	
CTS 3.0.7	974	Restrict POSIX FILE SYSTEM S_IS*() functions supported to a more limited set	
CTS 3.0.6	664	C/C++ FACE::Fixed Support Class More Than Container	
	826	TRANSMISSION_TYPE discrepency with MIL-STD-1553	
	936	Remove SCHED_SPORADIC from FACE profiles	
	943	Remove process groups functions from profiles	
	963	ARINC-429 LABEL_SEQUENCE should be unsigned long elements	
	990	The requirements for the operator[] override in the C++ header for String.hpp leads to confusing behavior	
	1023	pthread_cond_destroy() should not be in the Safety Base profile (all FACE editions)	

Table 17. Approved Corrections to the Technical Standard Addressed by Version of Test Suite

CTS Version	CR#	Consortium Title	
	518	C Library support for ARINC 653 Operational Environments is Ambiguous	
	809	Remove pthread_setconcurrency() and pthread_getconcurrency() from all profiles	
	902	Remove msync() from All Profiles	
	905	Remove SOCK_SEQPACKET from all profiles	
	910	Remove "shutdown" from "Security" and "Safety Base" profiles	
CTS 3.0.5	911	pipe() Should be Conditional on Multiple Process Support	
	918	CLOCK_THREAD_CPUTIME_ID Should Not be in any Profile	
	919	ARINC 653 C Library Should Not Include Timezone Support	
	921	POSIX Spawn Attribute Flags from Profiles that do not Have Methods to Manipulate Them	
	957	mlock/mlockall Included but Associated Constants are Not	
	970	Add More POSIX setsockopt() Option Values in FACE 3.0 and 3.1	
	564	TSS Interfaces Not Assigned to UoC	
	603	Remove confstr() from FACE Profiles	
	653	Not all TPMs should be required to provide Primitive_Marshalling	
	755	Union Accessors	
CTS 3.0.4	847	Add Support for explicit FACE::Fixed constructor for FACE::Float in FACE 3.0 and 3.1	
	848	Remove FACE_INTERFACE_NULL_THIS in FACE 3.0 and 3.1	
	849	Add Support for FACE String/Sequence reserve() methods in FACE 3.0 and 3.1	
	537	Serialize Incorrect Direction on Param	
	552	Sequence payload boundary initialization	
	569	Two FACE::TSS Common Types Should Be Unsigned	
	577	TA Send_Message_Blocking return_data Parameter Should be inout	
	580	TA Read_Callback Signature and Buffer Issues	
	600	TPM Callbacks can't create typed view	
	665	Initialization of Fixed Data Types	
	674	Sentinel Values for transaction_id when Publisher or Subscriber	
CTS 3.0.3	736	Extend setsockopt to include IPV6_JOIN_GROUP and IPV6_LEAVE_GROUP option value for General Purpose profile	
	742	Extend setsockopt to include IPV6_MULTICAST_HOPS option value for General Purpose profile	
	743	Constant FACE Strings Behavior is Not Fully Defined	
	746	Correct Inconsistent Definition of FACE_HMFM_RETURN_CODE_TYPE	
	824	Consider calling init() method for C Struct members of struct type	
	829	init() function for C structs should be "static inline" and not "extern inline"	

CTS Version	CR#	Consortium Title		
	225	Extend setsockopt API support to allow TCP protocol option for Safety Extended and General Purpose POSIX OSS Profiles		
	244	Verified that POSIX API macros identified in the FACE standard are properly defined		
	247	Verified that POSIX API function with expanded profiles in the FACE standard are properly defined		
	523	Ambiguous Reference to Sequence in OCL Constraint		
	531	Sequence and String Interface Specifications Too Limited		
	549	OCL constraints realizedCompositionsHaveDifferentTypes for Logical and Platform Entity contexts too restrictive		
	560	C sequence.h and string.h are missing extern C wrapper for use from C++		
	566	Describing Model association path of a participant's characteristic for more stringent rigor will cause a fail of the OCL		
	569	Two FACE::TSS Common Types Should Be Unsigned		
CTS 3.0.2	593	Header Guard Mapping Rules Violate C/C++ Language Standards		
	605	Process scheduling methods available when multiple processes are not supported		
	636	No epoch for time is given in the Technical Standard		
	637	Missing extern C in header files		
	705	Add TCP_NODELAY		
	708	FACE fixed.h has function defined twice		
	710	Unnecessary comma after last value in enum		
	711	FACE_FIXED_DIGITS_MAX in C++ conflicts with C macro		
	761	MIL-STD-1553 MAX_WORD_COUNT incorrect		
	789	Incorrect method specification for C sequence in Approved Correction for CR 531		
	551	Parameter mode problem in Get_Serialization		
	596	C++ Message Serialization Implementation Unable to Call Marshalling Methods		

CTS Version	CR#	Consortium Title	
	233	POSIX API Methods Required to be Macros Not in Appendix A	
	245	Add Additional POSIX APIs as applicable to Safety Extended Profile to Improve Alignment with SCA	
	246	Improve Consistency of General Purpose POSIX Profile in Appendix A.1	
	330	Make POSIX Processes Optional in Safety Extended and General Purpose Profiles	
	336	Add support of CAN BUS (ARINC 825) to the Technical Standard 3.0	
	350	Restrict mmap() Use to Shared Memory in Security and Safety Profiles	
	351	fork/exec Usage Restriction Lost	
	352	Appendix A.6 not Referenced in Requirements	
	353	Restrict posix_devctl() and select() related APIs to Sockets	
CTS 3.0.1	363	Add fdopen() POSIX APIs to Safety Extended Profile to Improve Alignment with SCA	
	366	LCM Does Not Apply to OSS	
	378	getservbyport() and getservent() should be marked Yes for IPC	
	379	pselect() is an IPC method but not in IPC restricted (limited) GSL libraries	
	380	socketpair() is an IPC method but not in IPC restricted (limited) GSL libraries	
	395	Update C and C++ Library Definitions to Include POSIX_C_LANG_SUPPORT_R functions	
	397	Clarify IDL module mappings to Ada packages	
	401	Valid IDL enumerations do not compile in Ada	
	416	Calling driver code from TSS TPMs	
	436	gethostname() should not be Inter-UoC restricted call	

CTS Version	CR#	Consortium Title	
	CR#	Consortium Title	
	219	FACE_sequence_return incorrectly defines FACE_STRING_NULL_THIS	
	234	Template Instantiation Naming Patterns	
	236	Define rules for IDL-generated file names	
	237	IDL for the template module instantiations should have been provided	
	240	Interface Class Instances Injected are Const and Cannot be used to invoke FACE Interfaces	
	241	Confusing Type Names in FACE::TSS::Typed	
	242	Ensure Data Model name is restricted or can be mapped into all programming languages	
CTS 3 0 0	260	FACE::String Missing Constructor for Constant Strings	
	263	Initialize(LCM::Initializable) cannot use Configuration Interface	
	264	C++ Sequence default constructor describes wrong bound	
	265	C/C++ Mapping for IDL array should not mention slice	
	268	C++ Mapping for IDL interface should have an inline empty destructor definition	
	269	Java mapping for unsigned integer types incorrect	
	273	Default definitions of C++ new need to be included	
	324	Directionality of transaction_id argument to Send_Message_Callback()	
	327	Directionality of buffer argument to Configuration::Read()	
	328	Component State Persistence arguments are incorrect	
	329	Directionality of buffer argument to TSS::CSP::Read()	

Appendix H: CTS Treatment of Default Values for Element/Composition Attributes

The FACE[™] metamodel is defined via Essential Meta-Object Facility (EMOF). EMOF supports specifying element/composition attribute default values and number of occurrences (i.e. lower/upper) constraints. The following discussion considers some examples of whether the EMOF defaults/constraints were applied properly in the CTS application, but the overall focus is to address how CTS handles default values. The CTS interpretation of the defaults/constraints may differ from EMOF because the CTS handling of default values is specified by the Java code that was generated from the EMOF. The generated code is used to read/write (i.e. deserialize/serialize) the .face XMI file.

The process for generating the Java code from the metamodel EMOF follows:

Using Eclipse:

- 1. Read the EMOF
- 2. Convert the EMOF model to an Eclipse Ecore model
- 3. Generate Java code from the Ecore model

The generated Java code is used by CTS to read (i.e. deserialize) the .face file. Therefore, the default values in the generated code determine the attribute values for attributes that are not present in the .face XMI.

Table 18 was built via parsing the generated Java code and extracting the default value fields. The table demonstrates that some of the corresponding default values align with the EMOF and some do not. For example, "Element description" in the EMOF and in the table defaults to "". A contrary case is "Logical RealRangeConstraint lowerBound", which has no default value in the EMOF, but does have a default value of 0.0F in the table.

A discussion of the implication of Java types on default values follows:

- *int/float/boolean* int/float/boolean are Java primitive types. In functions, Java requires that primitive types be initialized before they are used. Class attributes do not have to be initialized before they are used. Even if a Java primitive type was not initialized, it would have a value (e.g. type of int would be 0). For the values in Table 18, the Java primitive types were explicitly set in the code. Relying on default primitive values for unset primitives is not pertinent to the table. Therefore, even if the EMOF did not define a default value, a default value would exist in the Java code, which would handle the case where the attribute was not defined in the .face XMI.
- *String* The Java String type is a class and not a primitive type like int/float/boolean; therefore, String types can be null or populated. Before use, Java requires a String type to be defined with characters or set to null. In Table 18, some String types are set to "" and some to null. For example, in the EMOF and in the table "Conceptual Characteristic rolename" is set to "". Another example is "Conceptual Characteristic description", which has no default value in the EMOF and is null in the table.
- enum A Java enum has behavior similar to a Java String in that it can be null; however, the

generated code always defines a value. The default value is the first value in the list of literals defined in the EMOF.

Inheritance influences which attributes apply to a particular element. For example, ClientServerConnection extends (i.e. inherits from) Connection. This means that the Connection attributes are applicable to ClientServerConnection. See the "FACE Technical Standard", for a complete definition of the inheritance relationships.

Model	Element Name	Attribute Name	Java Type	Default Value
N/A	Element	name	String	
N/A	Element	description	String	
conceptual	Characteristic	rolename	String	
conceptual	Characteristic	lowerBound	int	1
conceptual	Characteristic	upperBound	int	1
conceptual	Characteristic	description	String	null
conceptual	CompositeQuery	isUnion	boolean	false
conceptual	Participant	sourceLowerBound	int	0
conceptual	Participant	sourceUpperBound	int	-1
conceptual	QueryComposition	rolename	String	
conceptual	Query	specification	String	null
logical	AffineConversion	conversionFactor	float	0.0F
logical	AffineConversion	offset	float	0.0F
logical	Characteristic	rolename	String	
logical	Characteristic	lowerBound	int	1
logical	Characteristic	upperBound	int	1
logical	Characteristic	description	String	null
logical	CompositeQuery	isUnion	boolean	false
logical	CoordinateSystem	axisRelationshipDescription	String	null
logical	CoordinateSystem	angleEquation	String	null
logical	CoordinateSystem	distanceEquation	String	null
logical	Enumerated	standardReference	String	null
logical	FixedLengthStringConstraint	length	int	0
logical	IntegerRangeConstraint	lowerBound	int	0
logical	IntegerRangeConstraint	upperBound	int	0
logical	MeasurementAttribute	rolename	String	null
logical	MeasurementConstraint	constraintText	String	null
logical	MeasurementConversion	conversionLossDescription	String	null
logical	MeasurementSystemConversion	conversionLossDescription	String	null
logical	MeasurementSystem	externalStandardReference	String	null
logical	MeasurementSystem	orientation	String	null
logical	Participant	sourceLowerBound	int	0
logical	Participant	sourceUpperBound	int	-1

Table 18. FACE 3.0 Attribute Default Values

Model	Element Name	Attribute Name	Java Type	Default Value
logical	QueryComposition	rolename	String	
logical	Query	specification	String	null
logical	RealRangeConstraint	lowerBound	float	0.0F
logical	RealRangeConstraint	upperBound	float	0.0F
logical	RealRangeConstraint	lowerBoundInclusive	boolean	true
logical	RealRangeConstraint	upperBoundInclusive	boolean	true
logical	ReferencePointPart	value	String	null
logical	RegularExpressionConstraint	expression	String	null
logical	StandardMeasurementSystem	referenceStandard	String	null
platform	Characteristic	rolename	String	
platform	Characteristic	upperBound	int	1
platform	Characteristic	lowerBound	int	1
platform	Characteristic	description	String	null
platform	CompositeTemplate	isUnion	boolean	false
platform	Composition	precision	float	0.0F
platform	Fixed	digits	int	0
platform	Fixed	scale	int	0
platform	IDLArray	size	int	0
platform	IDLBoundedString	maxLength	int	0
platform	IDLCharacterArray	length	int	0
platform	IDLComposition	rolename	String	null
platform	IDLComposition	precision	float	0.0F
platform	IDLSequence	maxSize	int	0
platform	Participant	sourceLowerBound	int	0
platform	Participant	sourceUpperBound	int	-1
platform	Query	specification	String	null
platform	TemplateComposition	rolename	String	
platform	Template	specification	String	null
integration	UoPInstance	configurationURI	String	null
traceability	TraceabilityPoint	rationale	String	null
traceability	TraceabilityPoint	reference	String	null
uop	ClientServerConnection	role	ClientServerRole	Client
uop	Connection	name	String	
uop	Connection	description	String	
uop	Connection	period	float	0.0F
uop	Connection	synchronizationStyle	Synchronization Style	Blocking
uop	LifeCycleManagementPort	messageExchangeType	MessageExchang eType	InboundMessage
uop	PubSubConnection	messageExchangeType	MessageExchang eType	InboundMessage
uop	QueuingConnection	depth	int	0

Model	Element Name	Attribute Name	Java Type	Default Value
uop	RAMMemoryRequirements	heapStackMin	int	0
uop	RAMMemoryRequirements	heapStackMax	int	0
uop	RAMMemoryRequirements	heapStackTypical	int	0
uop	RAMMemoryRequirements	textMax	int	0
uop	RAMMemoryRequirements	roDataMax	int	0
uop	RAMMemoryRequirements	dataMax	int	0
uop	RAMMemoryRequirements	bssMax	int	0
uop	SupportingComponent	version	String	null
uop	Thread	period	float	0.0F
uop	Thread	timeCapacity	float	0.0F
uop	Thread	relativePriority	int	0
uop	Thread	relativeCoreAffinity	int	0
uop	Thread	threadType	ThreadType	Foreground
uop	UnitOfPortability	transportAPILanguage	ProgrammingLa nguage	С
uop	UnitOfPortability	designAssuranceLevel	DesignAssurance Level	А
uop	UnitOfPortability	partitionType	PartitionType	POSIX
uop	UnitOfPortability	designAssuranceStandard	DesignAssurance Standard	DO_178B_ED_12 B
uop	UnitOfPortability	faceProfile	FaceProfile	GeneralPurpose